Mapbender Documentation

Release 4.0.0

The Mapbender Team

Jun 30, 2025

CONTENTS

1	Installation	1
2	Mapbender Quickstart: First steps with Mapbender	21
3	Elements	39
4	Backend	249
5	Customization / Tips and tricks	275
6	FAQ - Frequently Asked Questions	303
7	Architecture	309
8	Development	321
9	Version history	331
10	QGIS2Mapbender Plugin	355

CHAPTER

ONE

INSTALLATION

This page provides an overview over the different operating system installation instructions.

Installation and update guide for Mapbender users

1.1 Installation on Ubuntu/Debian

Mapbender is shipped with a preconfigured SQLite database which includes preconfigured applications (the database is located under *<mapbender>/var/db/demo.sqlite*). You can find instructions for a test installation based on the Symfony web server at *Launching Mapbender using the local Symfony web server*.

Hint: PostgreSQL is strongly recommended for productive use. Look up the neccessary configurational steps in the chapter *Optional > Mapbender Deployment on PostgreSQL*.

1.1.1 Requirements

- PHP >= 8.1
- Apache installation with the following modules activated:
 - mod_rewrite
 - libapache2-mod-php
- alternatively: nginx installation with the following modules activated:
 - php-fpm
- PostgreSQL Installation
 - It is recommended to use a PostgreSQL database for Mapbender.
 - It is recommended to create a database user to access the Mapbender database.

1.1.2 Preparation

Installation of mandatory PHP extensions:

```
sudo apt install php-gd php-curl php-cli php-xml php-sqlite3 sqlite3 php-apcu php-intl openssl php-zip□

→php-mbstring php-bz2
```

- Please check the FAQ Frequently Asked Questions for further PHP settings
- Please check API if you want to use the Mapbender API

1.1.3 Unpack and register to web server

Download the current Mapbender version and unzip it into /var/www/mapbender or a different location:

```
wget https://mapbender.org/builds/mapbender-starter-current.tar.gz -0 /var/www/mapbender-starter-

current.tar.gz
tar -zxf /var/www/mapbender-starter-current.tar.gz -C /var/www
mv $(ls -d /var/www/*/ | grep mapbender) /var/www/mapbender/
```

1.1.4 Configuration Apache 2.4

Create the file */etc/apache2/sites-available/mapbender.conf* with the following content:

```
Alias /mapbender /var/www/mapbender/public/
<Directory /var/www/mapbender/public/>
Options MultiViews FollowSymLinks
Require all granted
# Activate SetEnvIf if you want to use the Mapbender API
# SetEnvIf Authorization "(.*)" HTTP_AUTHORIZATION=$1
RewriteEngine On
RewriteBase /mapbender/
RewriteCond %{REQUEST_FILENAME} !-f
RewriteRule ^(.*)$ index.php [QSA,L]
</Directory>
```

Activate the site and reload Apache:

```
a2ensite mapbender.conf
service apache2 reload
```

1.1.5 Configuration nginx

As an alternative to apache2, nginx can also be used as webserver. To use Mapbender in nginx, create a configuration file within /etc/nginx/sites-available:

```
server {
    listen 80;
    listen [::]:80;
    server_name mapbender.localhost # change this to your needs
```

(continues on next page)

(continued from previous page)

```
# recommended to setup ssl here when not in a local environment
   root /var/www/mapbender/application/public;
   index index.php;
   location / {
       # First attempt to serve request as file, then
        # as directory, then redirect to index.php
       try_files $uri $uri/ /index.php$is_args$args;
   }
   # pass PHP scripts to FastCGI server
   location ~ \.php$ {
        include snippets/fastcgi-php.conf;
       fastcgi_pass unix:/run/php/php8.3-fpm.sock; # change this when using another PHP version
   }
    # deny access to .htaccess files, if Apache's document root
   # concurs with nginx's one
   location ~ /\.ht {
        deny all;
    }
}
```

Activate the new site and restart nginx:

```
ln -s /etc/nginx/sites-available/mapbender /etc/nginx/sites-enabled/
systemctl restart nginx
```

1.1.6 Directory rights

```
sudo chown -R :www-data /var/www/mapbender
sudo chmod -R ug+w /var/www/mapbender/var/log
sudo chmod -R ug+w /var/www/mapbender/var/cache
sudo chmod -R ug+w /var/www/mapbender/public/uploads
sudo chmod -R ug+w /var/www/mapbender/var/db/demo.sqlite
```

1.1.7 First steps

The Mapbender installation can now be accessed under http://[hostname]/mapbender/. User data by default:

- username: root
- password: root

Troubleshooting is available via the following command (must be executed in the application directory):

```
bin/console mapbender:config:check
```

Hint: Please note that config:check will use the php-cli version. The settings may be different from your webserver PHP settings. Please use php -r 'phpinfo(); ' to show your PHP webserver settings.

Congratulations! Mapbender is now set up correctly and ready for further configuration. Find Information about the first steps with Mapbender in the *Mapbender Quickstart*.

1.1.8 Optional

LDAP

To use the optional LDAP-connection, following PHP-LDAP-extension is required:

sudo apt install php-ldap

Note: To use LDAP, the LDAP-Bundle must be integrated into Mapbender. Further setup instructions can be found in the Bundle's README.md on GitHub.

Mapbender installation with PostgreSQL

Configuration of PostgreSQL database for productive use:

Requirements:

- Installation of PostgreSQL
- database for the Mapbender configuration
- PostgreSQl database user to access the database (optional)

Installation PHP-PostgreSQL driver

sudo apt install php-pgsql php_pdo_pgsql

Configuration of database connection is done by a variable that contains the entire connection string. Configure it by adding it in your *.env.local* file.

For further information: YAML Configuration (Configuration and Application files).

Create Mapbender database if it does not exist already:

cd /var/www/mapbender
bin/console doctrine:database:create

Create mapbender table structure and load example applications

```
cd /var/www/mapbender
bin/console doctrine:schema:create
bin/console mapbender:database:init -v
bin/composer run reimport-example-apps
```

Create root user for access:

bin/console fom:user:resetroot

Find further information in Details of the configuration of Mapbender.

1.2 Installation on Windows

Mapbender needs a database to store information. The Mapbender download package contains a SQLite database that is ready to use. For production we recommend the use of a PostgreSQL database.

1.2.1 Requirements

- PHP NTS >= 8.1 (https://windows.php.net/download/)
- Apache installation (https://www.apachelounge.com/download/, run as service with these modules):
 - mod_rewrite
 - mod_fcgid
- PostgreSQL Installation (https://www.enterprisedb.com/downloads/postgres-postgresql-downloads)
 - It is recommended to use a PostgreSQL database for Mapbender.
 - It is recommended to create a database user to access the Mapbender database.
- As a web server, you can also use nginx, which is considered a beta version for Windows. If you still want to use it, you can use the same configuration file as in the Linux installation guide.

1.2.2 Configuration PHP

- Unzip the Zip archive, for example under c:\php.
- Depending on the PHP version, PHP variables for a temp directory are not set correctly under Windows.
- Therefore, it has to be checked if the following variables (php.ini) are set correctly:

```
sys_temp_dir
upload_tmp_dir
date.timezone
```

- The path from PHP-bin directory to the PATH variable (Windows environment variable) needs to be set.
- Activate the required PHP extensions in the *php.ini* configuration file:

```
# php.ini
extension=php_curl
extension=php_fileinfo
extension=php_gd
extension=php_intl
extension=php_pdo_pgsql
```

(continues on next page)

(continued from previous page)

```
extension=php_pdo_sqlite
extension=php_pgsql
extension=php_openssl
extension=php_mbstring
extension=php_zip
extension=php_bz2
```

- Please check the FAQ Frequently Asked Questions for further PHP settings
- Please check API if you want to use the Mapbender API

1.2.3 Extract Mapbender and register to web server

Download the current Mapbender version and unzip it into c:\mapbender

1.2.4 Configuration Apache

A subfolder conf.d must be prepared in the directory <apache>/conf.

Add the following code at the end of file *httpd.conf*:

Include directory conf.d
Include "conf/conf.d/*.conf"

Create file <apache>\conf\conf.d\mapbender.conf with:

```
Alias /mapbender c:/mapbender/public/
<Directory c:/mapbender/public/>
Options MultiViews FollowSymLinks
Require all granted
# Activate SetEnvIf if you want to use the Mapbender API
# SetEnvIf Authorization "(.*)" HTTP_AUTHORIZATION=$1
RewriteEngine On
RewriteBase /mapbender/
RewriteCond %{REQUEST_FILENAME} !-f
RewriteRule ^(.*)$ index.php [QSA,L]
</Directory>
```

Restart Apache.

1.2.5 mod_fcgid

Create file <apache>\conf\conf.d\fcgi.conf with:

```
LoadModule fcgid_module modules/mod_fcgid.so

FcgidInitialEnv PHPRC "c:/php/"

FcgidInitialEnv PATH "c:/php;C:/WINDOWS/system32;C:/WINDOWS;C:/WINDOWS/System32/Wbem"

FcgidInitialEnv SystemRoot "C:/Windows"

FcgidInitialEnv TEMP "C:/WINDOWS/TEMP"

FcgidInitialEnv TMP "C:/WINDOWS/TEMP"
```

(continues on next page)

(continued from previous page)

FcgidInitialEnv windir "C:/WINDOWS" FcgidPassHeader Authorization FcgidIOTimeout 1200 FcgidConnectTimeout 1200 FcgidBusyScanInterval 1200 FcgidBusyTimeout 1200 FcgidErrorScanInterval 1200 FcgidIdleScanInterval 1200 FcgidIdleTimeout 1200 FcgidZombieScanInterval 1200 FcgidMaxProcesses 1000 FcgidOutputBufferSize 64 FcgidProcessLifeTime 3600 FcgidMaxRequestsPerProcess 10000 FcgidMinProcessesPerClass 0 FcgidFixPathinfo 0 MaxRequestLen 200000 <Files ~ "\.php\$"> Options Indexes FollowSymLinks ExecCGI AddHandler fcgid-script .php FcgidWrapper "c:/php/php-cgi.exe" .php </Files>

1.2.6 Configuration PostgreSQL

Configuration of PostgreSQL database for productive use:

Requirements:

- Installation of PostgreSQL
- database for the Mapbender configuration
- PostgreSQl database user to access the database (optional)

Activate the PHP-PostgreSQL driver

```
# php.ini
extension=php_pgsql
extension=php_pdo_pgsql
```

Configuration of database connection is done by a variable that contains the entire connection string. Configure it by adding it in your *.env.local* file.

```
MAPBENDER_DATABASE_URL="postgresql://dbuser:dbpassword@localhost:5432/dbname?serverVersion=17&

→charset=utf8"
```

For more information on the database configuration, see YAML Configuration (Configuration and Application files).

Open the windows shell.

Create the Mapbender database if it does not exist already:

```
cd c:\mapbender
php.exe bin/console doctrine:database:create
```

Create the Mapbender table structure and the load example applications:

```
cd c:\mapbender
php.exe bin/console doctrine:schema:create
php.exe bin/console mapbender:database:init -v
php.exe bin/composer run reimport-example-apps
```

To administrate Mapbender you need a user. Create root user for access:

php.exe bin/console fom:user:resetroot

Find further information in Details of the configuration of Mapbender

1.2.7 First steps

The Mapbender installation can now be accessed under http://[hostname]/mapbender/.

Check if the alias is working

- http://localhost/mapbender/
- username: root
- password: root

Troubleshooting is available via the following command (must be executed above the *bin*/ directory):

php.exe bin/console mapbender:config:check

Hint: Please note that config:check will use the php-cli version. The settings may be different from your webserver PHP settings. Please use php -r 'phpinfo(); 'to show your PHP webserver settings.

Further information can be found at *bin/console mapbender:config:check*.

Congratulations! Mapbender is now set up correctly and ready for further configuration. Find information about the first steps with Mapbender in the *Mapbender Quickstart*.

1.3 Update Mapbender to a newer Version

To update Mapbender you have to do the following steps:

- Get the new version.
- Save your **configuration files** (*parameters.yml* for versions < 4.0.0 respectively *.env.local* for >= 4.0.0, and the files from the folder *config/packages*) and your old Mapbender version (files and database).
- Replace the old with the new Mapbender files.
- Merge your configuration files (check for new parameters and changes).

Warning: If you are migrating to Mapbender version 4, please read the *note in the migration guide* before upgrading the database!

• Update your Mapbender database.

- Copy the **screenshots** from your old Mapbender version from */public/uploads/* (respectively, *web/uploads* for < 4.0.0) to the folder */public/uploads* of your new installation.
- **Templates**: If you are using your own template, you have to compare your scripts with the new scripts (are there any changes?).
- **Print templates**: If you use your own print templates, copy them back to *con-fig/MapbenderPrintBundle/templates/*.
- Import the demo applications: either via bin/composer run reimport-example-apps or via the web administration.
- At *Unpack and register to web server*, you can see how the config file for the Apache Alias should look like.

And that's all! Have a look at your new Mapbender version.

Hint: Please follow the migration instructions on specific Mapbender versions, see the Migration Guide.

1.3.1 Update Example for Linux

Have a look at the steps as commands

```
# Download the new version
wget http://mapbender.org/builds/mapbender-starter-current.tar.gz /tmp/build_mapbender/
tar xfz /tmp/build mapbender/mapbender-starter-current.tar.gz
# save the old version
mv /var/www/mapbender /var/www/mapbender save
# get the code of the new version
cp -R /tmp/build mapbender/mapbender-starter-v4.0.0 /var/www/
mv /var/www/mapbender-starter-v4.0.0 /var/www/mapbender
# transfer your old configuration information to the new version
# transfer the information from config/parameters.yml to .env.local resp. /config/parameters.yaml
# transfer the information from old config.yml to /var/www/mapbender/config/packages/doctrine.yaml
# manual step
# merge parameters.yaml, doctrine.yaml and other YAML files you use
# if you use screenshots: copy the screenshots from the old version back to mapbender/public/uploads
# if you have individual templates: merge the templates with the new Mapbender version
# if you use your own print templates: copy them back to config/MapbenderPrintBundle/templates/
# change the accessrights and owner of the files
sudo chmod -R ugo+r /var/www/mapbender
sudo chown -R :www-data /var/www/mapbender
# Update your Mapbender database
cd /var/www/mapbender/
bin/console doctrine:schema:update --complete --dump-sql
bin/console doctrine:schema:update --complete --force
# Import the mapbender demo applications
bin/composer run reimport-example-apps
```

(continues on next page)

(continued from previous page)

```
# Update the symbolic links
bin/console assets:install public --symlink --relative
# change the access rights and group of the files
sudo chmod -R ug+r /var/www/mapbender
sudo chown -R :www-data /var/www/mapbender
# You have to set write permission to var/cache and var/log.
sudo chmod -R ug+w /var/www/mapbender/var/cache
sudo chmod -R ug+w /var/www/mapbender/var/log
sudo chmod -R ug+w /var/www/mapbender/var/log
sudo chmod -R ug+w /var/www/mapbender/public/uploads
```

1.3.2 Update Example for Windows

```
# Download the new version http://mapbender.org/builds/
# Save the old version (files and database)
# Copy the configuration files (parameters.yaml and files from folder config/packages) to your new \square
\rightarrow Mapbender version.
# You have to check the configuration files for changes (new parameter, other changes)
# Call the bin/console commands with php.exe
# You have to open a windows console to send the commands
c:
cd mapbender
# Update your Mapbender database
php.exe bin/console doctrine:schema:update --complete --dump-sql
php.exe bin/console doctrine:schema:update --complete --force
# Import the mapbender demo applications
php.exe bin/composer run reimport-example-apps
# Export files to the web-directory
php.exe bin/console assets:install public
# Delete your cache and the logdateien at mapbender/var/cache und mapbender/var/log
# if you use screenshots: copy the screenshots from the old version back to mapbender/public/uploads
# if you have individual templates: merge the templates with the new Mapbender version
# if you use your own print templates: copy them back to config/MapbenderPrintBundle/templates/
```

Installation guide and details for developers

1.4 Launching Mapbender using the local Symfony web server

Launching Mapbender on the local Symfony web server allows for quick configuration using Symfony's native mechanisms. This enables you to perform tests without the need to integrate it into a separately set up web server.

Note: The local web server bundle has been removed and replaced with the local Symfony web server. Install the Symfony CLI development tool to use it.

Hint: The use of the Symfony built-in web server is not suitable for production environments.

In this document we assume that the SQLite database is used.

- Please check the installation documentation for *Linux* respectively *Windows*.
- Download the current Mapbender build <https://mapbender.org/builds/>.
- Extract Mapbender in an arbitrary directory.
- Start the installed local Symfony web server.

symfony server:start --no-tls

The command runs a local web server, so that Mapbender is available on the local machine. By default, the server listens on 127.0.0.1 address and the port number is automatically selected as the first free port starting from 8000.

Note: Please note that you can pass the application environment (prod or dev) with the command below.

APP_ENV=prod symfony server:start --no-tls

You could also change the default port by passing it as an argument. For more options, check the --help flag:

```
symfony server:start --no-tls -port=8002
```

```
[OK] Web server listening
The Web server is using PHP CLI 8.2.10
http://127.0.0.1:8002
```

1.5 Git-based installation

Note: The Git-based installation is intended for Mapbender development or project-specific customizations that can be stored in a cloned Mapbender Starter. There, you can add your own printing templates, applications, or bundles. You can then load Mapbender and any other modules you need (e.g., Digitizer) using Composer. When updating Mapbender, compare the status of the Mapbender Starter repositories. The basic customizations can be done by chcecking the versions in the *composer.json* file. All essential information is documented by the Mapbender team on GitHub. The key documentation files and their contents include:

- README.md describes the installation from the Git sources of the Mapbender Starter Git repository.
- CHANGELOG.md lists changes between the different Mapbender versions.
- UPGRADING.md provides important information on Mapbender installation upgrades to specific versions.
- The Contributing Guide presents the software architecture and the steps involved in developing Mapbender.
- The /docs/-README.md is the entry page for the technical documentation of Mapbender.

1.6 Details of the configuration of Mapbender

1.6.1 Configuration steps

In the following, we will describe the configurational steps of Mapbender a bit further. Configuring your Mapbender installation consists of the following six steps:

- Creating the database
- Creating the database schema
- Copying the bundles' assets into the *public* directory
- Creating the "root" user
- Initializing the database
- Loading the demo applications to your database

All that can be done using the console utility provided by Symfony, on which the Mapbender framework is built upon. There's some mayor caveats though you should understand before continuing:

Note: The console utility will write files in the var/cache and var/log directories. These operations are made using the user permissions of whatever user you're logged in with. This is also true for the var/db directory and the SQLite database within. When you open the application from within the browser, the SQLite database with its server PHP process will try to access/write all these files with other permissions. So make sure you give the PHP process write access to these files. See last step below.

Note: Important: The following steps assume that you are in the directory above the *bin* directory (for git installation that means in *mapbender/application/*, otherwise *mapbender/*).

cd mapbender/
or for git based installation
cd mapbender/application

Adapting the configuration file

Database connection parameters are stored together in the file *.env.local*. Other configuration parameters are defined in the file *parameters.yaml* and other files in the *config* directory.

More Information: YAML Configuration (Configuration and Application files).

Creating the database

Hint: In general, it is recommended to create the database using a graphical database tool such as, for example, pgAdmin.

Alternatively, Symfony can attempt to create your database, this works of course only if the configured database user is allowed to do so. Call the console utility like this:

bin/console doctrine:database:create

Creating the database schema

Symfony will create the database schema for you:

bin/console doctrine:schema:create

Copying the assets bundles

Each bundle has its own assets - CSS files, JavaScript files, images and more - these must be copied into the *public* folder:

bin/console assets:install public

Alternatively, as a developer, you might want to use the symlink switch on that command to symlink instead of copy. This will make editing assets inside the bundle directories way easier.

bin/console assets:install public --symlink --relative

Creating the administrative user

The first user - which has all privileges - must be created using the command:

bin/console fom:user:resetroot

This will interactively ask all information needed and create the user in the database.

Alternatively, there is a silent mode you can use, if you want to use a script to install Mapbender and don't want to be asked for all parameters:

bin/console fom:user:resetroot --username="root" --password="root" --email="root@example.com" --silent

Initialize the database

Initializing the database can be done using the command:

bin/console mapbender:database:init

Importing applications

It is possible to (re-)import applications from the *applications/* folder into the database with the command:

bin/composer run reimport-example-apps

1.6.2 Configuration files

The configuration files are located in the *config/* folder.

Find more information in: YAML Configuration (Configuration and Application files).

Also have a look at the .env.local and the .env file at application/.

1.6.3 Production and Development environment and Caching

Mapbender provides two environments: a production environment for the general operation and a development environment in which the application can be tested. This concept follows the Configuration Environments in the Symfony framework.

The production environment is called with the URL http://localhost/index.php, the development environment with the URL http://localhost/index_dev.php. The call with index_dev.php is restricted and should only be available from localhost. You can modify the *index_dev.php* file and add IP addresses to be able to access the development environment from other locations.

There are differences in the behaviour of the production and development environment:

• The cache mechanism of the development environment behaves differently: Not all files are cached, thus code changes are directly visible. Therefore, the usage of index_dev.php is always slower than the production environment.

In detail, the development environment of Mapbender does not cache the CSS, JavaScript and Translation files, among others.

The production environment caches all these files and puts them into the *var/cache* folder.

- The development environment gives out error messages and stack traces to the user interface. The production environment logs them into the file *var/log/prod.log*.
- The development environment shows the Symfony Profiler. This tool logs things that are important for developers but are not supposed to be visible for common users.

The directory *var/cache* contains the cache files. It contains directories for each environment (prod and dev). But the mechanism of the dev cache, as described before, behaves differently.

If changes of the Mapbender interface or the code are made, the cache directory (*var/cache*) has to be cleared to see the changes in the application.

The environment can be set via the APP_ENV variable. Make sure to change this to *prod* when deploying your application for the public. The value can be changed in several ways:

- by overriding the value in an .env.local file,
- by setting an environment variable in your Apache2 vHost configuration: SetEnv APP_ENV prod,
- by explicitly setting it when starting the local webserver:

```
APP_ENV=prod symfony server:start --no-tls
```

1.7 Migration Guide

Hint: This page gives migration instructions on specific Mapbender versions. For general tips on updating, see the *Update Mapbender to a newer Version* page instead.

Tip: For in-depth information from the Mapbender development team, also see the Upgrading Guide on GitHub.

1.7.1 Migration to Mapbender 4.0.0

- Carefully check the Upgrading Guide on GitHub before you do the update.
- You will notice that the Symfony Directory Structure changed a lot.
- For Mapbender 4, all .yml file extensions were transformed into .yaml.
- *config.yml* is omitted.
- public files moved from web/ to public/.
- Instead of multi parameters in *parameters.yml*, the database definition is replaced by an environment variable MAPBENDER_DATABASE_URL. Configure it by adding it in your *.env.local* file. If you have multiple connections, use one env variable per connection and configure these in the *config/packages/doctrine.yaml* file.
- The Apache Vhost Definition or ALIAS has to be changed. Refer to *public* (instead of *web*). Call index.php instead of app.php). See *installation instruction*.
- Environment can now be set using the environment variable APP_ENV (see *.env.local*), .index_dev.php (instead of app_dev.php) is still available as an alternative for accessing the dev environment.
- Database permission can be migrated using bin/console mapbender:security:migrate-from-acl. Do that before executing the schema:update command, otherwise your old ACL tables will be gone!

Upgrade database

Warning: Execute the following commands in the specified order to upgrade (after bringing the symfony directory structure up to date). First, make a backup of your database!

1. Replace Doctrine's removed json_array type to json. If you are using a DBMS other than SQlite, PostgreSQL and MySQL, you need to do that manually:

bin/console mapbender:database:upgrade

2. Migrate security definitions from the ACL system to the new permission system:

bin/console mapbender:security:migrate-from-acl

3. Update the rest of the database. This must be executed last, since it deletes the old ACL tables:

```
bin/console doctrine:schema:update --complete --force`
```

1.7.2 Migration to Mapbender 3.3.4

• Please update the database schema. Run:

```
bin/console doctrine:schema:update --force
```

• Next, you need to configure CSRF tokens to be used during login to the **csrf_token_generator** form_login section in *security.yaml* as follows:

```
form_login:
    check_path: /user/login/check
    login_path: /user/login
    csrf_token_generator: security.csrf.token_manager
```

• For productive environments, it is important to install an SSL certificate. After that, set the parameters.cookie_secure variable in your *parameters.yaml* to true. This ensures that the Login cookie is only transmitted over secure connections.

1.7.3 Migration to Mapbender 3.3

- Make sure you have PHP >= 7.4 or PHP 8.x.
- Provide a backup of your database.
- Update your database schema to 3.3 with bin/console doctrine:schema:update --force.
- *doctrine.yaml*: Please note that in the doctrine connection configuration variables must be set with quotes, for example '%database_driver%'
- CAUTION: Please note that the eye at application is used from (3.2.x) onwards to make the application available for the anonymous user (public access). Before 3.2.x, the eye/checkbox at **Security** was used to publish an application.

To update from 3.2.x to 3.3.x should be quite easy.

Note: If you update from a version < 3.2, you have to follow the steps described at the *Migration to Mapbender 3.2* section below.

1.7.4 Migration to Mapbender 3.2

You can migrate older Mapbender installations to Mapbender 3.2.

Check the Update Mapbender to a newer Version Guide.

- Make sure you have PHP >= 7.1.0 and PHP < 8.
- Provide a backup of your database.
- Update your database schema to 3.2 with bin/console doctrine:schema:update --force.
- CAUTION: Please note that the eye at application is from (3.2.x) used to make the application available for the anonymous user (public access). Before the eye/checkbox at Security was used to publish an application.

Some elements may not work after the update and may need a closer look.

Update map_engine_code

If it makes sense, update all applications to map_engine_code current.

Update mb_core_application set map_engine_code = 'current';

SearchRouter

In the Workshop bundle, you can find a Demo.

- 1. deprecated empty: use placeholder instead
- 2. For text and choice you have to define the full class-path.

You also find information at Best Practices Page.

You can update the configuration with the following SQL.

```
Update mb_core_element set configuration =
replace(configuration,'s:6:"choice"','s:53:"Symfony\Component\Form\Extension\Core\Type\ChoiceType"')
where class = 'Mapbender\CoreBundle\Element\SearchRouter';
Update mb_core_element set configuration =
replace(configuration,'s:4:"text"','s:51:"Symfony\Component\Form\Extension\Core\Type\TextType"')
where class = 'Mapbender\CoreBundle\Element\SearchRouter';
```

Select configuration from mb_core_element where class = 'Mapbender\CoreBundle\Element\SearchRouter';

3. For choice: Please note that key or value are passed flipped that means value and the key- see also Best Practices Page

choices: Bonn - this is the value not the key: Bonn Cologne - this is the value not the key: Cologne Siegburg - this is the value not the key: Siegburg

Migrating SimpleSearch

SimpleSearch element was improved. You can now define the projection of the result that comes from the Solr Service. Mapbender will then transform the result to the projection of the map.

SimpleSearch Supports Nominatim, Photon from version 3.2.5 - see workshop demo applications

1. Define sourceSrs in your SimpleSearch definition. If not defined, the default ('EPSG:4326') should be chosen. You can find an example at this Configuration file

sourceSrs: 'EPSG:25832'

2. query_ws_replace: From version 3.2.8 on, set query_ws_replace or modify the code as described in this issue comment

query_ws_replace: +

Migrating BaseSourceSwitcher

Please note that on start of an application, all WMS are activated where the root layer is activated.

Before 3.2, it was possible to activate all BaseSources, where only the first WMS was visible on start.

Template / CSS

CSS change. Plus, there will be a big redesign in backend and frontend in the upcoming versions.

- Check the workshop Bundle for the changes
- Define your template as desktop-template

Migrating Digitizer

Digitizer is available for Mapbender >= 3.2.2. The new Digitizer Version is 1.4. Some functionality is not updated to 1.4 already (e.g. cluster).

- See list of deprecated features
- See also digitizer php file
- You can find a demo in the Workshop bundle
- maxResults is supported again to limit the number of features that are loaded to the application (if not defined all features will be used) (digitizer >=1.4.9)
- For font definitions, see issue 1308
 - fontSize: 38 definition without px
 - labelxOffset: 18 (not supported in 3.2.3)
 - labelYOffset: 18 (not supported in 3.2.3)
- Types that are not supported in 3.2.4
 - upload
 - select with multiselect
 - coordinates
- Clustering not implemented in 3.2.x

- Style definition is limited not all OL2 styles can be defined
- Support styling features with icons (interpret externalGraphic, graphicWidth, graphicHeight properties) (Mapbender >= 3.2.7)
- Support data placeholder syntax in externalGraphic (e.g. "/bundles/projectbundle/images/\${type}.png") (Mapbender >=3.2.7)
- Save NULL for empty fields, works for int/float/decimal columns but not for double precision (Mapbender >= 3.2.6, see issue 1355)
- Save NULL for empty fields for text fields does not work. Mapbender saves " instead (see issue 1385)
- supports printable: true

There is a new style called unsaved.

```
unsaved:
    strokeWidth: 3
    strokeColor: "#f0f0f0"
    fillColor: "#ffff"
    fillOpacity: 0.5
    pointRadius: 6
    label: 'Neu - bitte speichern'
    fontColor: red
    fontFamily: 'Arial, Courier New, monospace'
    fontColor: red
    fontSize: 38
    fontWeight: bold
```

WMS Layer visibility

Make sure that your WMS provides a proper extent for all supported EPSG-codes (this is used and saved in table mb_wms_wmslayersource columns latlonbounds and boundingboxes). Else it can happen that a layer is not requested for the given extent of your map.

Notice on the Sketch element

Redlining was renamed to Sketch (>= 3.2.3).

```
Update public.mb_core_element set class = 'Mapbender\CoreBundle\Element\Sketch',
title = 'mb.core.sketch.class.title'
    where class = 'Mapbender\CoreBundle\Element\Redlining';
```

FeatureInfo

- showOriginal deprecated parameter not available anymore (from 3.2.3).
- highlighting: true new >= 3.2.3 highlights the geometry if you have WKT integrated in the featureinfo result - see issue 1287 and also this FeatureInfo blog post

Print - Print queue

- Mapbender supports print queue
- see Queue blog post



CHAPTER

TWO

MAPBENDER QUICKSTART: FIRST STEPS WITH MAPBENDER

Mapbender is a web based geoportal framework to publish, register, view, navigate, monitor and grant secure access to spatial data infrastructure services. Management interfaces empower administrators who need to maintain and categorize map and feature services and grant access to individuals, groups and other services. Mapbender is written from the ground up using modern web technologies. The foundation is laid by Symfony. On the client-side expect to find OpenLayers.

With this code base, we will continue the Mapbender idea of being a Geoportal framework. Key features of Mapbender are:

- Applications can be setup, configured and styled right from within the browser.
- Services (e.g. WMS) can be managed inside a service repository and linked to applications.
- Rights management are easy to maintain, for individual users and groups, whether you store them inside the database or in an LDAP.
- Search modules can be configured.
- Applications for digitalization can be setup.
- Mobile template can be used to provide applications for smartphones and tablets.

You will need nothing but a web browser for this quickstart.

This quickstart offers sections to:

- 1. Start Mapbender
- 2. Create an application
- 3. Add elements to your application
- 4. Configure Sources
- 5. User and group management
- 6. Rights management
- 7. Start an Application at a defined position

This is how a Mapbender application can look like:



2.1 Install Mapbender

This quickstart explains the basics of Mapbender and serves as a quick introduction after your first successful *Installation*.

2.2 1. Start Mapbender

- Choose Mapbender from the start menu (if a shortcut was already created) or visit http://localhost/ mapbender (this address can be slightly different depending on how the Apache Alias was created in the file /etc/apache2/sites-available/mapbender.conf. Find more information under Installation).
- 2. The application should then appear in your browser window.

If you have any difficulties running Mapbender, please check whether your Apache web server and your PostgreSQL database are running without errors.

2.2.1 Start Mapbender in a productive environment

Mapbender offers two environments: **dev** (this is the default) and **prod**.

The development environment shows full error messages including stack traces in the browser and enables the Symfony debug console and profiler. Also, caching is disabled. The productive environment enables caching and only shows generic error messages. More specific error messages are written into logfiles.

The environment can be set via the APP_ENV variable. Make sure to change this to prod when deploying your application for the public. The value can be changed in several ways:

• by overriding the value in an .env.local file,

- by setting an environment variable in your Apache2 vHost configuration: SetEnv APP_ENV prod,
- by explicitly setting it when starting the local webserver:

```
APP_ENV=prod symfony server:start --no-tls
```

2.2.2 Mapbender Backend

- 1. After a successful Mapbender startup, the application overview page in the *Backend* will appear. The applications are listed with a screenshot, title, URL title and description.
- 2. You can open an application by clicking on its title, its screenshot or via
- 3. A login is required to gain access into Mapbender's *Backend*. In order to do so, click on Login at the top-right of the login page. You can login with the user that was generated during installation. This could be **root** with the password **root**. This is the default user and password that you get after installation of Mapbender. Please change the root password if you want to run a productive environment.

Warning: Do not delete the root user.

After a successful login you will be directed to the *Backend*.

2.2.3 Application overview

The **Applications** page displays a list of all available applications. The root user has access to the following functions:

- Title, URL title and description
- Preview screenshot for the application
- Filter textfield for application search

Button to create new applications
 Button to show an application
 Button to duplicate an application
 Button to export an application
 Button to edit an application

0	OBULTION TO MAKE AN APPLICATION AVAILABLE FOR THE PUBLIC						
Din Mapbender	Button to dele	ete an application		ه Logged in as: root ج			
	Applications						
	+ New Application		FilterQ				
		Demo URL Title: mapbender_user Description: Full desktop application showing most of the standard Mapbender elements	۵ و				
		Basic demo URL Title: mapbender_user_basic Description: Simple desktop application					

2.3 2. Create an application

There are three different options to create an application:

An application can be created out of an already existing one. This can be done via a click on the application overview. The application will receive the same title and URL title with the appendix **_imp**, or **_db** (for yaml applications). All previously defined elements and configurations will be transferred as well.

Another possibility is the import of an application. Further information can be found under YAML Configuration (Configuration and Application files).

Furthermore, new applications can be created from scratch. The required steps are explained in the following:

- 1. Select the option **New Application** in the application overview.
- 2. After that, select a template in order to define the layout of your application. The options are: Fullscreen, Fullscreen alternative, Mapbender Mobile template. It is also possible to define your own template and assign it to a new application.

Tip: Please note that the style-, icon- and layout-configurations can be set up online via the CSS editor tab and/or via configuration files locally. Read more about template generation under *How to create your own Template*?

- 1. Define a title, URL title and a description (optional). Title and URL title can be identical. However, the URL title has to follow the usual URL syntax: Typically, lowercase letters, numbers, as well as hyphens and underscores are allowed.
- 2. A thumbnail can be uploaded as well. It will appear next to the application title on the application overview page. For this, select **Select File** below the thumbnail section.

٢C

- 3. Set the checkmark at **Persistent map state** to make certain map parameters and configurations persistent. Further information can be found in *Share elements*.
- 4. Set the checkmark at **Show Splashscreen** to generate a loading screen on application startup that indicates the loading time.
- 5. Click **Save** to save and create your application. It is now possible to add elements (e.g. map, navigation bar, legend) and services to your application.

se data Layouts Layersets CSS Security Title* Mapbender Demo	Q View
Title* Mapbender Demo	
URL Title* mapbender_demo Thumbnail Durchsuchen Keine Datei ausgewählt. Description Mapbender demo application showing many elements in action Persistent map state Show Splashscreen	

2.4 3. Add elements to your application

Mapbender applications consist of a Top toolbar, Sidepane, Map area and Footer. A variety of different elements can be added into these areas.

1. Choose **Applications** []

🛛 Layouts.

2. Click on

to get an overview over the elements Mapbender provides.

Note: Mapbender provides different regions in your application. Not all elements can be added to all regions.

- 1. Choose an element from the list. Make sure to add the element to a region that makes sense.
- 2. Configure the element.

Note: When you select an element, for example *Map*, you see that the element has a set of attributes. Each element offers individual attributes for configuration.

- 1. You can change the position of an element via drag & drop within and between regions.
- 2. Have a look at your application. To open your application, click on

Now you should have an idea about how easy it is to change a Mapbender application.

Applications Sources Security		
	Add element Toolbar	
Mapbender Der	Filter	
Base data Layouts Laye	About dialog Shows an about dialog	Ulew
	Activity indicator Shows HTTP activity	Template: Fullscreen
Toolbar _{Title}	Application switcher Switches to another application while maintaining current map position	۰ +
Featureinfo Print client Image export	Base source switcher Change the map's background sources.	• C P • 4 8 • C P • 4 8 • C P • 4 8
Legend WMS loader CPS Position	Button Controls another element	
measure measure about	Coordinates display The coordinates display shows your mouse position in map coordinates.	
POI	Coordinates utility	• [] 🖵 o 🔍 🖹
Sidepane	Cancel	0

In the following, you find a complete list of all elements and their functionalities. For a more detailed description, please have a look at the corresponding chapters in the *Table of Contents*.

- About Dialog: Show information about Mapbender in an about dialog.
- Activity Indicator: Shows HTTP activity.
- Application Switcher: Switch to another application while maintaining the current map position.
- *Button*: Integrate another element as a button.
- *Base source switcher*: Change the map's background sources.
- Coordinates Utility: Transform coordinates to different SRS and navigate to them on the map.
- Coordinates Display: Show the map coordinates of your mouse position.
- Copyright: Shows terms of use.
- Data Manager: Create and save information in a database.*
- Digitizer: Create and manage spatial data.*
- Dimensions handler: Manage sources with a time dimension.
- Image Export: Export the current map view (format options: .png or .jpeg)
- Legend: Displays legend of active themes on the map.

- *Link*: Links to an external URL.
- Layertree: Lists all included layer sets and layers with selection and sorting options.
- Map: Creates the map element in which layersets and layers are integrated into.
- Overview: Provides an overview map.
- POI: Create a POI for sharing.
- PrintClient: Renders a Print dialog.
- Line/Area Ruler: Enables to measure a line/area and display its length/area in a dialog.
- *Scale Display*: Displays the current map scale.
- *Scale Bar*: Displays a small line indicator representing the current map scale.
- *Scale Selector*: Displays and changes a map scale.
- Search Router: Enables a configurable search via SQL.
- Simple Search: Enables a configurable search on JSON sources (e.g. Solr).
- *Simple Search*: Enables a search.
- *Sketches*: Enables a drawing tool with different shapes.
- *SRS Selector*: Changes the map's spatial reference system.
- *Share URL*: Share the current map view via URL.
- View Manager: Save map states for later restoration.
- *WMS Loader*: Load a WMS via a getCapabilities-Request.

Hint: Items marked with an asterisk (*) require additional dependencies.

2.5 4. Configure Sources

Mapbender can handle sources of the type OGC WMS or OGC WMTS / TMS. Via a click on **Sources**, you can navigate to an overview of all uploaded sources. There is a second list called **Shared instances** which only provides sources of the type shared. Further information about bound and shared instances can be found under *Layerset*.

Sources provides the following functions:



• filter via text to search for sources

Sources	
Sources Shared instances	
+ Add source	FilterQ
Mapbender User ^{#25}	
Iype: WMS 1.3.0 URL: https://wms.wheregroup.com/cgl-bin/mapbender_user.xml?VERSION=1.3.0 Abstract: Mapbender User Reference	
#10	
OpenStreetMap (OSM) Demo WhereGroup #19 Type: WMS13.0	
URL: https://osm-demo.wheregroup.com/service?VERSION=1.3.0	
Abstract: This is an OpenStreetMap Demo Service of WhereGroup	

2.5.1 Load sources

Mapbender allows the integration of OGC Web Map Services (WMS) and Web Map Tile Services (WMTS). Versions 1.0.0 and 1.3.0. are supported. A source provides a XML when its getCapabilities document is requested. This information is then read by Mapbender: The client receives all necessary information about a source via this XML.

Tip: You should check your capabilities document in your browser before uploading the service.

- 1. To upload a source, click on **Add source**.
- 2. Define the **Type** of the source: OGC WMS or OGC WMTS / TMS.
- 3. In the field **Service URL**, provide the link to the getCapabilities URL.
- 4. Define username and password (in case your source requires it).
- 5. Click on **Load** to upload the service into the repository.
- 6. After a successful upload, Mapbender will provide an overview of the WMS information.

dd source	
Type *	
OCC WMS	~
Service URL *	
http://osm-demo.wheregroup.com/service?SERVICE=WMS&Version=1.3.0&REQUEST=GetCapabilities	
Username	
Password	
	Load Cancel

2.5.2 Add sources to an application

After uploading a service, it can be integrated into one or several application(s).

1. Navigate to **Applications**. Click on

of the desired application and navigate to **Layersets**.

- 2. In **Layersets** you can integrate uploaded sources into your application. Click on next to the filter function to create a layerset. All layers have to be assigned to at least one layerset. Provide a name for it (e.g. *main* for the main map and *overview* for the overview map).
- 3. Now you can add layers to the layerset. Click on next to the desired layerset.
- 4. The order of the layers can be changed via drag & drop.

emo		vie
Filter main		+ + ≎ 0 ₪
Id Title	Source	Туре
51 OpenStreetMap (OSM) Demo WhereGroup	#6 OpenStreetMap (OSM) Demo WhereGroup	🔥 WMS 🥝 🌣 🛍
50 Mapbender Users	#5 Mapbender Users	မီ WMS 🥥 🌣 🕅
overview		+ 🂠 🗹 🔟
Id Title	Source	Туре
52 OpenStreetMap (OSM) Demo WhereGroup	#6 OpenStreetMap (OSM) Demo WhereGroup	🖧 WMS 🥥 🌣 🕅

2.5.3 Source configuration

Sources can be individually configured. This can be useful if you, for instance, don't want to display all layers, change the order or titles of the layers, prevent a layer's feature info output or adjust the scale in which the layers are visible.



- 2. You can now change the instance configuration.
- 3. The order of the layers can also be changed via drag & drop.

	up.com/cgi-bin/mapbender_user.xml								Save	Dace
Title *			Dimensions							+
Mapbender Users										
Opacity			Vendor specific							+
85		0	Page Course							
Format *										
image/png		~								
Infoformat			☑ Transparency							
text/html		~	L filed							
text/num		•	Layer ordering *							
Exceptionformat			standard							•
		~								
Tile buffer										
Tile buffer		0								
Tile buffer 0 3BOX factor		\sim								
Tile buffer 0 3BOX factor 1.25		0								
rile buffer 0 3BOX factor 1.25		0								
rile buffer 0 3BOX factor 1.25 Title	Minsc	0	Maxsc	active	sele	ect	inf	fo	tog	gle
rile buffer 0 3BOX factor 1.25 Title	Minsc	0	Maxsc	active	sele	ect on	inf allow	fo on	tog	gle on
rile buffer 0 3BOX factor 1.25 Title	Minsc	•	Maxsc	active	sele allow	ect on	inf allow	fo on	tog allow	gle on
rile buffer 0 3BOX factor 1.25 Title Mapbender Users	Minsc	0	Maxsc	active	sele allow S	ect on 2	inf allow	fo on O	tog allow	gle on
rile buffer 0 BBOX factor 1.25 Title Mapbender Users Vuser	Minsc		Maxsc	active 2 2	sele allow	on I I I I I I I I I I I I I I I I I I I	inf allow	Foon	tog allow 2	gle on

Source configuration:

- **Title**: Name of the application.
- Opacity: Opacity in percentage (0: transparent, 100: opaque).
- Format: Format of the getMap-Requests.
- Infoformat: Format of the getFeatureInfo-Requests (text/html is recommended).
- Exceptionformat: Format for error messages.
- **Tile buffer**: This parameter is valid for tiles services and specifies if additional tiles should be requested. If the user pans the map, these tiles are already downloaded and visible. The higher the value the more tiles are requested (default: 0).
- **BBOX Factor**: This parameter is valid for non-tiled WMS services. You can specify the size of the returned map-image. A value greater than 1 will request a bigger map-image (default: 1.25).
- **BaseSource**: If active, the service is handled as a BaseSource. Should be activated for full-screen background maps, such as street maps and satellite images, and where a simultaneous display is not needed.
- **Proxy**: If active, the service will be requested by Mapbender and not directly. Should always be enabled for password-protected services, as otherwise the password will be readable by every user.

- **Transparency**: Default is *active*, the source is without a transparent background if it is deactivated (getMap-Request with Transparent=FALSE).
- **Tiled**: You can request a WMS in tiles, default is not tiled (may be a good choice if your map is very big and the WMS service does not support the width/height).
- **Layer ordering**: Handles the order of the layers in the service. Can be set to *standard* (reversed) and *QGIS* (same order).

Dimensions:

This function is relevant for sources with a time dimension. Further information can be found under *Dimensions handler*.

Vendor Specific Parameter:

You can define Vendor Specific Parameters in a layerset instance to add them to a WMS request. This principle follows Multi-Dimensions in the WMS specification.

You can use Vendor Specific Parameters in Mapbender to add the user and group information of the logged-in user to a WMS request. You can also add hard coded values.

List of the possible parameters:

- User: \$email\$, \$groups\$, \$id\$, \$username\$
- Groups: \$id\$, \$title\$, \$description\$

The following example shows the definition of the parameter groups, which transfers the group value of the logged-in user.

Vendor specific						
+						
Vstype	user	~	×			
Name	groupIds					
Default	\$groups\$					
🗌 Hidden						

- Vstype: Mapbender specific variables. Group (groups), User (users), Simple
- Name: Parameter name of the WMS request
- Default: Default value
- **Hidden**: If this value is set, requests are send via a server so that the parameters are not directly visible. Only works if **Proxy** is enabled for the service, too.

Currently, the element can be used to transfer user- and group information, e.g. for a user the \$id\$ and for groups the value \$group\$.

Layer configuration:

- title: Layer title as shown in the layer tree. Default value is the getCapabilities requested title.
- min./max. scale: scale scope (e.g., 1:100-1:1000).
- **active on/off**: activates/deactivates a layer completely.
- **select allow**: layer is active when the application starts.
- **select on**: selectable in geodata explorer.
- **info allow**: layer info is active when the application starts.
- info on: layer provides feature info requests, info default activates the feature info functionality.
- **toggle allowed**: allows opening in the layer tree.
- **toggle on**: open folder on start of the application.
- more information (...): opens a dialog with detailed layer information.
 - ID: ID of the layer. Can be useful *to control* URL parameters.
 - Name: layer name of the service information (for getMap-Requests).
 - **Style**: if a WMS provides more than one style you can choose a different style than the default style.

2.6 5. User and group management

Access to Mapbender requires authentication. Only public applications can be used by everyone. A user can get permissions to access one or a set of applications and services.

2.6.1 Create a user

- 1. To create a user, go to **Security** [] **Users** [] **Add new user**.
- 2. Choose a name for your user.
- 3. Provide an email address for the user.
- 4. Choose a password for your user and repeat it in the **Confirm password** field.
- 5. Save your new user. It is still possible to alter user information later on.

Mapbender Applications Sources Security	💄 Logged In as: root 👻
New User	
Base data Profile Groups	
User name*	
E-Mail*	
Choose password*	
Confirm password*	
☑ activated	
	Save Cancel

You can provide more information about the user in the tab **Profile**. In the **Groups** and **Security** tabs it is possible to assign the user additional parameters, e.g. the membership to a group.

adata Brafila Graupe	
Filter	
Name	1 groups of 5 selected
A-Team	
Application editors	
Mapbender Team	
🗆 Team 7	
Test accounts	

2.6.2 Create a group

- 1. Create a group by **Security** [] **Groups** [] **Add new Group**.
- 2. Define a name and a description for your group.
- 3. In the tab **Users**, assign users to your group.
- 4. Save your new group.

2.7 6. Rights management

Mapbender provides an easy-to-use rights management that is implemented into the backend.

- View: Select a user that is allowed to view an object (e.g., an application or a service).
- Create: Select a user that is allowed to create an object.
- Edit: Select a user that is allowed to make changes to an object.
- Delete: Select a user that is allowed to delete an object.

Hint: Assign rights to a user via Security [] Global Permissions.

2.7.1 Assign an Application to a User/Group

1. Edit your application via **Application**



3. Make your application accessable to the public by **Security** [] **Public Access**. Alternatively, one can



2. Choose Security.

Toggle public access.

4. Alternatively to public access, you can set permissions for specific users/groups:

🕹 Mapbender	Applications Sources	Security					💄 Logged in	as: root 🔻
Ba	asic Demo)						
Bas	e data Layouts	Layersets CSS	Security				Uiew	
							+	
	Filter		View 🕑	Edit 🕑	Delete	Permission Management 🜑		
	L Mallory		View	Edit	Delete	Permission Management	Û	
	L Bob		View	Edit	Delete	Permission Management	Û	
	L Alice		View	Edit	Delete	Permission Management	Û	
	L root		View	Edit	Delete	Permission Management	Û	
							Save Cancel	

Test your configuration. Logout from Mapbender by clicking **Logout** in the upper right corner. Login again as the new user.

2.7.2 Assign elements to a User/Group

Per default, all elements of an application are accessible to users and groups if they have access to that particular application. This can be modified for each element.

- Edit your application by clicking Edit.
 In your application settings, choose Layouts.
 For every element, it is possible to Restrict element access.
 Choose the Restrict element access from the element that should be only available for special users/groups.
- 5. Assign one or more users or groups to the element. Then, you can set a **View** permission for the specific users or groups.
- 6. Test your configuration.

2.8 7. Start an Application at a defined position

You can open an application at a defined location. This can be done by a POI. You also can add texts in the request.

You can pass one or more POIs in the URL. Each POI has the following parameters:

- point: coordinate pair with values separated by comma (mandatory)
- label: Label to display (optional)
- scale: Scale to show POI in (optional, makes only sense with one POI)

If you pass more than one POI, the map will zoom to 150 % of the POIs bounding.

To pass a single POI, use the following URL format:

• ?poi[point]=363374,5621936&poi[label]=Hello World&poi[scale]=5000

2.9 What's next?

This is only the first step on the road to using Mapbender. There is a lot more to discover:

- Head over to the official Mapbender website,
- Find quick answers to the biggest Mapbender-related questions in the FAQ Frequently Asked Questions,
- Become a member of the Mapbender community.

CHAPTER

THREE

ELEMENTS

3.1 Base elements

3.1.1 Activity Indicator

The activity indicator element provides a simple widget showing background activity (Ajax calls and pending map tile requests). In the default configuration it uses a Font symbol.

The activity indicator can be implemented in footer, sidepane and toolbar. Per default it looks like this:

ं

Configuration

Add elen	ndicator
Title	Activity indicator
Tooltip	mb.core.activityindicator.class.title
CSS-Class General	mb-activity
Activity	
CSS-Class Background	mb-activity-ajax 🚱
Activity	
Loading	mb-activity-tile
	Back Add Cancel

- **Title:** Title of the element.
- **Tooltip:** The text entered as a tooltip will be indicated by hovering over the element with the mouse cursor a longer time.
- Activity class: CSS class to indicate activity (Ajax or tile).
- Ajax activity class: CSS class to indicate Ajax activity.
- **Tile activiy class:** CSS class to indicate tile loading activity.

YAML-Definition

This template can be used to insert the element into a YAML application.

```
activityClass: mb-activity # CSS class to indicate activity (Ajax or tile)
ajaxActivityClass: mb-activity-ajax # CSS class to indicate Ajax activity
tileActivityClass: mb-activity-tile # CSS class to indicate tile loading activity
```

3.1.2 Base source switcher

Base source switcher is a group of buttons that enables the user to switch between different predefined services (BaseSources), e. g. background maps. For every sourceset a button will be displayed in the client. Only one sourceset is active at the same time. Moreover, it is possible to define groups. All sourcesets of the same group will be listed in a dropdown list with the group name as the title.



Hint: Base source switcher can also be added into the sidepane. The definition of groups is not possible in the sidepane.

BaseSourceSwitcher

OSM

- O DOP
- O no background

Configuration

Preparation: In order to be able to configure the Base source switcher, you have to define service instances as BaseSource (checkbox "Basesource"). You can define the layer as a BaseSource in the *Layerset* tab in the *Backend* of the application. You have to edit the service and set a check mark at "BaseSource".

SM Demo			Convert to shared instant
Origin URL: https://osm-demo.wheregroup.com/service Title* OSM Demo Opacity 100 Format of the GetMap request* image/png Format of GetFeatureInfo request	3	 + Vendor specifics PaseSource Proxy Transparency Tiled Layer ordering* standard 	Save Back
text/html Exception format Tile buffer	 		
0 BBOX factor 1.25			

Note: On application start, all sourcesets with an activated root layer will be active.

Configuration with selected root layer - sourceset is active on start:

[Title	Minsc	Maxsc	active	sele	ct	inf	;o	tog	gle	
					allow	on	allow	on	allow	on	
					<	~					
	CSM Demo				•						
	OSM Demo WhereGroup				2	2					

Configuration with selected root layer - sourceset is not active on start:

Title		Minsc	Maxsc	active	select	info	o	tog	gle	
					allow on	allow	on	allow	on	
					•					
	CSM Demo									
	OSM Demo WhereGroup				•••					

The configuration of the element itself occurs in two steps:

- 1. Create a Base source switcher element with Title, Tooltip (and, if configured in Map area: Position)
- 2. Add sourceset(s) with one or more sources and definition of a group (optional)
- **Title:** Title of the element.
- **Tooltip:** The text entered as a tooltip will be indicated by hovering over the element with the cursor.
- **Instancesets:** One or more instancesets can be defined. Select one or more instances and assign a title and group (optional).

Edit elem	ient	
Title	mb.core.basesourceswitcher.class.title	
Tooltip	mb.core.basesourceswitcher.class.title	
Instancesets* +		
Title*	OSM (color)	Û
Group	mb.demoapps.baseMaps	
Instances*	OSM Demo OSM Demo OSM Demo	
Title*	OSM (greyscale)	Û
Group	mb.demoapps.baseMaps	
Instances*	OSM Demo OSM Demo OSM Demo	
Title*	OSM (transparent)	Û
Group	mb.demoapps.baseMaps	
Instances*	OSM Demo OSM Demo OSM Demo	
	Save Cano	cel

In the configuration example either one, none or several entries per instanceset can be selected. You can

create groups, which are then grouped together in the dropdown list. Further Instancesets can be added

via the button. It is possible to move an instanceset in the configuration window via drag and drop.

- **Title**: Title of the BaseSource.
- Group: Optional group name.
- **Position:** Position (only when used in Map area). Options: 'left-top', 'right-top', 'left-bottom', 'rightbottom'
- Instances: Sources for the BaseSource.

YAML-Definition

This template can be used to insert the element into a YAML application.

```
title: 'BaseSourceSwitcher'
                                                     # title
tooltip: 'BaseSourceSwitcher'
                                                     # text to use as tooltip
target: map
                                                     # Id of Map element
anchor: 'right-bottom'
                                                     # Position (only when used in Map area). Options:
→ 'left-top', 'right-top', 'left-bottom', 'right-bottom'
sourcesets:
                                                     # List of sourcesets
    - { title: sourcesetname, group: groupname,
        sources: [sourceId]}
                                                     # sourceset: title.
                                                     # group: (optional) group name to group of
→ sourcesets by "group name"
                                                     # sources list of sources
  sourcesets:
    - { title: sourcesetname, group: groupname,
        sources: [sourceId]}
```

3.1.3 Coordinates Display

The element shows your mouse position in map coordinates. The coordinates are dependent on the selected spatial reference system which may be changed with the *SRS Selector* element. Used together with Coordinates Display gives the added functionality of being able to switch between different coordinate systems.

The coordinates display for different coordinate systems looks like this:

ETRS89 / UTM zone 32N (EPSG:25832):

DHDN / 3-degree Gauss-Kruger zone 2 (EPSG:31466):

```
WGS 84 (EPSG:4326):
```

🔁 x: 7.0921068 y: 50.7250737	WGS 84	\sim	
	ase-Web		
WGS 84 / Pseudo-Mercator (EPSG:3857	7):		
• x: 789487.28 y: 6572806.51	WGS 84 / Pseudo-Mercator	~	

Configuration

Edit elem	ient
Show label	
Title	Coordinates display
Number of decimal places*	0
Empty	x: - y: -
Prefix	x:
Separator	у:
	Save Cancel

• **Show label:** Show a label which incorporates the title and appears next to the coordinates.

• **Title:** Title of the element. It will appear next to the coordinates if "Show label" is activated.

- Number of decimal places: Number of decimal digits of the coordinates.
- Empty: Text displayed when the mouse is not on the map (default: 'x = y = -').
- Prefix: Prefix in front of the X coordinate (default: '= x').
- Separator: Separator in between the X coordinate and Y coordinate (default: 'y= ').
- **Position:** Position (mandatory field, only when used in Map area). Options: 'left-top', 'right-top', 'left-bottom', 'right-bottom'.

YAML-Definition

This template can be used to insert the element into a YAML application.

<pre>numDigits: 2</pre>	# the number of digits each coordinate shall have when being rendered $lacksquare$
→(default: 2)	
target: map	# id of Map element to query
label: true	<pre># true/false to label coordinates display (default: false)</pre>
empty: 'x= - y= -'	# show this text if the mouse is not on the map
<pre>prefix: 'x= '</pre>	# show prefix before x coordinate
separator: ' y= '	# show separator before y coordinate
<pre>anchor: 'right-bottom'</pre>	<pre># Position (only when used in Map area). Options: 'left-top', 'right-top</pre>
\leftrightarrow ', 'left-bottom', 'right-bot	tom '

CSS-Styling

The element can be customized with the following CSS-style, for example to increase the width.

```
.mb-element-coordsdisplay {
    width: 500px;
}
```

3.1.4 Data Upload

Data Upload allows you to upload geodata as points, lines, polygons and multipolygons. Supported geodata file formats are GeoJSON, KML, GML, and GPX. Simply drag and drop the files into the element or choose them from within a file manager window. You can either choose a fitting CRS or use the feature *Determine projection automatically.*

Hint: File size is limited. A maximum file size can be defined in the element configuration.



Configuration

Add elem Sidepane - Data U	pload	
Title	Data Upload	
Max. filesize (MB)*	10	
Help text	mb.core.dataupload.admin.helpText	
	Back Add Cancel	

- **Title**: Title of the element, appears in the header of the element.
- Max. filesize (MB): Maximum permitted file size in megabytes. Default: 10 MB.
- Help text: Define a help text that is displayed above the upload field of the element.

After **Data Upload** has been added to the backend, it is displayed at the corresponding position in Mapbender. After an object is uploaded, it will be shown in the map and the element list. There, you can toggle its visibility, zoom to it, or delete it again.

YAML Definition

This template can be used to insert the element into a YAML application.

3.1.5 FeatureInfo

FeatureInfo offers the possibility of obtaining information about features with a mouse click on a layer. The element works with supported WMS services. It can be integrated into the sidepane or within a *Button*.

WMS Krankenhäuser NRW	۲ <u>۲</u>	
		2
WMS Kranken	näuser NRW	
ID:	3140625	
Bezeichnung Kranke	nhaus: LVR-Klinik Bonn	1 Salaten -
Telefon:		Kenner
Webadresse:		BONN
Art:	Plankrankenhaus	
Träger:	LVR-Klinik Bonn	
Rechtsform:		
Bezeichnung Betrieb	sstätte: LVR-Klinik Bonn	
PLZ:	53111	rersitat
Adresse:	Kaiser-Karl-Ring 20	smpus jelsdorf
<u></u>	Dana	X

The WMS Krankenhäuser NRW from 'Ministerium für Gesundheit, Emanzipation, Pflege und Alter NRW' serves as example service.

Configuration

Add ele	ement atureInfo			
Activate au	utomatically	Deactivate on close	Print resu	lt 🗌 Only valid
Title	Featurel	nfo		
Display type*	Tabs			~
Max count	100			\$
Width*	700			\$
Height*	500			\$
Highligh	i ting ng enabled			
Default			On hove	г
Stroke color	rgba(255,68,1	02,0.4)	Stroke color	rgba(255,0,0,0.7)
Stroke	1		Stroke	3
(pixels)			(pixels)	
Fill color	rgba(255,165	,0,0.4)	Fill color	rgba(255,0,0,0.7)
				Back Add Cancel

- Activate automatically: Enable or disable autoopening of the copyright window when starting the application (default: false).
- **Deactivate on close:** true/false to deactivate the functionality after closing the result dialog (default: true).
- **Print result:** Offer a link to print the result of FeatureInfo (default: false).

- Only valid: Display valid WMS (default: false).
- **Title:** Title of the element. It will be indicated next to the button.
- **Display type:** Display of the information either in different tabs or in an accordion.
- Max count: Maximum number of results that should be displayed in the result dialog.
- Width/Height: Width/height of the dialog in px.
- Highlighting enabled: Deactivates/activates FeatureInfo Highlighting (default: false).
- Default stroke color: Sets the stroke color for selected objects.
- Stroke width (pixels) of the default color: Sets the stroke width (in pixels) of the default color.
- Default fill color: Sets the fill color for selected objects.
- Hover stroke color: Sets the hover stroke color for selected objects.
- Stroke width (pixels) of the hover color: Sets the stroke width (in pixels) of the hover color.
- Hover fill color: Sets the hover fill color for selected objects.

Layertree settings

The layer is visible and FeatureInfo request for the layer is activated.





The layer is invisible and there will be no FeatureInfo request (even if FeatureInfo request is activated).



Printing the results

The switch **Print result** allows you to print the output of the FeatureInfo. A Print button will appear on the FeatureInfo dialogue. The printing itself will be processed via the printing dialogue of your web browser.

To make sure that all images and background colors are available in your printout, you should check the print settings of your web browser: In Firefox, you can check the option "Print background". In Chromebased browsers the option is called "Background graphics". The used fonts can vary on a printout as PDF and depend on the specific viewer. Furthermore, most web browsers modify the pages a bit before printing to save ink/toner.

FeatureInfo Highlighting

Individual geometries of a WMS can be highlighted with FeatureInfo. This is particularly helpful for the work with comprehensive WMS, because it allows an easier identification of geometries.

A FeatureInfo request with activated highlighting could look like this:



The figure above highlights several geometries in the map (Postcodes ('PLZ'): 53111, 53113 und 53115). The FeatureInfo dialog only displays information belonging to these geometries. The area 53115 is highlighted red due to hovering.

FeatureInfo Highlighting is activated within the Feature Info element. Here, users get the option to choose a default and hover color.

Furthermore, the HTML output of the FeatureInfo request has to be adjusted. In order to do so, the geometry query has to be hidded as a WKT in an HTML div (will not be displayed). In addition, the EPSG code must be transferred and there must be a unique ID in the HTML div (see configuration below). Mapbender evaluates this information and displays the geometries on the map. When you hover over the entries in the info window, the associated geometry is highlighted accordingly. The adaptation looks different depending on which WMS server software you are using. Adjustments can easily be made for MapServer, QGIS Server, GeoServer.

The necessary adjustment is shown here using a configuration for MapServer. In the DATA specification, the geometry is put out as a WKT. In addition, the FeatureInfo template is adapted. If a WMS is now queried via GetFeatureInfo, the corresponding areas are highlighted on the map. You also could add data-label to define a labeling.

```
DATA "geom from (Select *, ST_AsText(geom) as geom_wkt from plz) as foo USING UNIQUE gid USING SRID 4326

↔"

<div class="geometryElement" id="[gid]" data-geometry="[geom_wkt]" data-srid="EPSG:4326" data-label=

↔"[beschriftung]" >
```

(continues on next page)

(continued from previous page)

•••			
,	 	 	

YAML-Definition

This template can be used to insert the element into a YAML application.

title: FeaureInfo	# title of the element
tooltip: Feature Info	# text to use as tooltip
type: dialog	# defines the element type (default: dialog)
target: map	# Id of Map element to query
<pre>autoActivate: false</pre>	<pre># true/false open when application is started (default: false)</pre>
<pre>deactivateOnClose: true</pre>	# true/false to deactivate the functionality after closing the result
→dialog (default: true)	
onlyValid: false	<pre># require correct HTML format of response (default: false)</pre>
<pre>printResult: false</pre>	<pre># offer a link to print the result of the featureInfo (default: false)</pre>
displayType: tabs	# tabs/accordion (default: tabs)
width: 700	# width of the dialog in pixels (default: 700)
height: 500	<pre># height of the dialog in pixels (default: 500)</pre>
maxCount: 100	<pre># maximum count of hits to be displayed</pre>
highlighting: false	<pre># deactivates/activates FeatureInfo Highlighting (default: false)</pre>
<pre>fillColorDefault: '#ffff00'</pre>	<pre># fill color to highlight selected objects</pre>
<pre>strokeColorDefault: '#ff00ff'</pre>	<pre># stroke color to highlight selected objects</pre>
opacityDefault: 25	<pre># opacity for fill color of selected objects</pre>
<pre>strokeWidthDefault: 3</pre>	<pre># line width to highlight selected objects</pre>
<pre>fillColorHover: '#00ffff'</pre>	<pre># fill color to highlight selected objects during hovering</pre>
<pre>strokeColorHover: '#0000ff'</pre>	# stroke color to highlight selected objects during hovering
opacityHover: 50	<pre># opacity for fill color of selected objects during hovering</pre>
<pre>strokeWidthHover: 5</pre>	# line width to highlight selected objects during hovering

3.1.6 Layertree

Functions

- Display layers
- Display layergroups
- Display thematic layergroups
- Enable and disable layers
- Enable and disable queries for layers
- Change the order of layers
- Zoom to map extent of a layer
- Query the metadata of a layer
- Control the time dimension of a layer

Please also configure the elements below that are connected to the Layertree:



Fig. 1: Layertree as a dialogue popup showing services with layers.



Fig. 2: Thematic Layertree integrated in the sidebar displaying the layerset titles.

- Layerset
- *Map*
- Sources

Configuration

General Configuration

To use the different Layersets in our Layertree, various adjustments are necessary. These relate to:

- 1. Configuration of various Layersets
- 2. Configuration of the map to display the Layersets
- 3. Configuration of the Layertree itself

Layers are included in the application via the Layerset tab in the Backend.

The instances are the references to the individual WMS services. With , new Layersets can be created. New layers can be integrated in the application by adding registered instances into Layersets. In the example, the Layerset "overview" is used for displaying the overview map. For a detailed documentation on how the services can be integrated and registered correctly, please head over to the *Layerset* and *Sources* documentation.

Demo		
Base data Layouts Layersets CSS Security	•	View
Filter	-	+
main	+ 🌣 🗹 🕅	Î
Id Title Source	се Туре	
51 OpenStreetMap (OSM) Demo WhereGroup #6 Op Where	ipenStreetMap (OSM) Demo 🖞 WMS 🥥 🌣 🕻 reGroup	Û
50 Mapbender Users #5 Ma	Iapbender Users 🕹 WMS 🥥 🌣 🖡	ÎÌ
overview	+ 🌣 🗹 🗊	Î
Id Title Source	се Туре	
52 OpenStreetMap (OSM) Demo WhereGroup #6 Op Where	ipenStreetMap (OSM) Demo 🔥 WMS 🥥 🌣 🛿 reGroup	Û
	Save	Cancel

Fig. 3: Configuration of various Layersets for integration into the Layertree.

In order to let the newly integrated Layersets appear in the application, they must be specified in the *Map element*. Here, you define which Layersets you want to use in the map by checking the boxes in the list. For example, the Layerset "overview" is not displayed on the main map. In this step, you define the order in which the Layersets appear in your Layertree and the map. You can move the created Layersets from the list by drag & drop.

Workflow Layertree with basic functions

In the following section, we walk through an exemplary configuration of a Layertree with basic functions in three steps:

- 1. Configuration of a Layerset
- 2. Configuration of the map to display the Layerset
- 3. Configuration of the Layertree itself

Configuration of a Layerset

In the example, we defined one **Layerset** with one instance:

- Layerset World:
 - Instance OSM Demo Service

The registered instance of the OSM Demo Service is automatically included in Mapbender's installation. The WMS only has to be integrated into an existing Layerset. Switch to the tab Layersets. The following example uses the Layerset "World". In case of difficulties with the integration, *Layerset* provides useful information.

Configuration of the map to display the Layerset

In the next step, we configure the *Map element* to display the Layersets in the **Map**. To do this, you need to switch to the **Layouts** tab and edit the map element in the map area. It is important that you activate the checkbox next to the "World" Layerset so it appears in the application afterwards.

If you have questions for further configuration, the *Map element* documentation can help.

Configuration of the Layertree itself

The last step is the configuration of the **Layertree** itself. The instances specified in the map element can be defined in more detail with the Layertree. If a predefined application has been copied, the Layertree should already work. If the element is newly created, it can already be used with the default settings without necessary further adjustments. For a better understanding of the functions and their usage, we now edit the backend's Layertree element in the map area.

By enabling **Show base sources**, instances that have been loaded as a base source in the application are displayed in the Layertree.

If you activate **Autoopen**, the Layertree is open by default and does not need to be activated by clicking on a button or the unfolding of a sidepane. The **Title** of the element is displayed in the *Layouts* list and allows you to distinguish between different layertrees.

Via the **Menu** a number of functions can be activated, which are then available in the layertree.

- Remove layer: Remove a layer from the application session
- Opacity: Change the opacity of a layer
- Zoom to layer: Zoom to full layer extent
- Metadata: Show the metadata of the layer

Edit eler	ment						
Title	Мар						
Layersets*	✓ World Overvie	ew					
Tile size	512						
SRS*	EPSG:385	7					
Max. extent*	min x*	-20037508.342789	min y*	-20037508.342789	0		
	max x*	20037508.342789	max y*	20037508.342789			
Start extent*	min x*	772933.16	min y*	6566826.23	0		
	max x*	806786.66	max y*	6582317.62			
Default Resolution [dpi]*	96				0		
 Fixed zoom s 	steps						
Scales	5000000	5000000,25000000,10000000,5000000,1000000,500000,100000,50000,25000,1000					
(comma- separated)*							
Other SRS	EPSG:258	32,EPSG:25833,EPSG:3146	56,EPSG:31467,	EPSG:4326			
				Save	Cancel		

Fig. 4: Configuration of the Layersets in the map element.

Mapbender		
Base data Layouts Layersets CSS Security		Uiew
Filter		+
Overview		+ 🌣 🗹 🛍
Id Title	Source	Туре
53 OSM Demo	#1 OSM Demo	பீ WMS 🛛 🌣 🛍
World		+ 🌣 🗹 🕅
Id Title	Source	Туре
57 OpenStreetMap (OSM) Demo WhereGroup	#6 OpenStreetMap (OSM) Demo WhereGroup	မီ WMS 🞯 🌣 🛍
		Save Cancel

Fig. 5: Configuration of a Layerset for integration into the Layertree.

- **Dimension**: Change the dimension, e.g. time or elevation of the Layer. Read more about the *Dimensions handler*.
- Select style: Allow the option to change the style of a layer if the layer offers multiple styles.

The individual functions can be activated by clicking on the buttons. All active functions are highlighted. In addition, a symbol of the context menu appears next to each layer in the Layertree. By clicking on the menu, a window pops up and the individual features can be used. The menu can be closed by clicking on the x-button.

The function **Hide info** allows you to disable the "i"-icon. If enabled, the "i"-icon next to a layer name indicates if the FeatureInfo function is active for that layer. The function is inactive if the "i"-icon is grayed out. If you activate the function with a click, the icon will turn dark gray and be framed. If activated, the requested information of the layer appears in a dialogue box.

The checkbox **Thematic layer** activates the thematic division of levels. By clicking on the folder icon of the Layertree to the left of the instance, the embedded layers can be displayed. All layers that have been previously activated in the Layerset now appear in the list.

The checkbox **Allow Reorder at TOC** controls if layers are rearrangeable via drag & drop in the application's layertree (TOC).

The checkbox next to its respective layer name allows to turn a layer on and off. If the checkbox is set, the Layer will appear on the map. However, it will continue to respect the defined rules of the Layerset (such as scale-dependent display).

Hint: With the 4.1.0 Version you now have the ability to Toggle the state of all sublayers when holding shift while toggling a layer.

Edit eler	ment				
Title	Мар				
Layersets*	✓ World○ Overvie	ew			
Tile size	512				
SRS*	EPSG:385	7			
Max. extent*	min x*	-20037508.342789	min y*	-20037508.342789	8
	max x*	20037508.342789	max y*	20037508.342789	
Start extent*	min x*	772933.16	min y*	6566826.23	8
	max x*	806786.66	max y*	6582317.62	
Default Resolution [dpi]*	96				0
Fixed zoom s	iteps				
Scales	5000000),25000000,10000000,500	0000,1000000,	500000,100000,50000,250	00,100(
separated)*					
Other SRS	EPSG:258	32,EPSG:25833,EPSG:3146	6,EPSG:31467,	EPSG:4326	
				Save	Cancel

Fig. 6: Configuration of the map element to display the Layerset.

Add elen Sidepane - Layer t	nent	
Open automat	tically 🕑 Show base sources	
Title	Layer tree	
Menu	Remove layer Opacity Zoom to layer Metadata Dimension Select style	
🗌 Hide info 🗌) Thematic layer	
Themes	element - Layer tree automatically Show base sources Layer tree Remove layer Opacity Zoom to layer Metadata Dimension Select style nfo Thematic layer World C C	
✓ Allow Reorder	r at TOC	
	E	Back Add Cancel

Fig. 7: Configuration of the simple Layertree in the map area.

Menu	Remove layer Opacity Zoom to layer Metadata Dimension Select style
------	---

Fig. 8: Configuration for the context menu.



Fig. 9: Context menu of the layer in the Layertree.

🖿 🖸 OpenStreetMap (WhereGroup)	≡
🗹 i OpenStreetMap	≡
☑ i OpenStreetMap (grey scale)	\equiv

Fig. 10: Layertree Buttons.

Workflow thematic Layertree

In the following section, we walk through an exemplary configuration of a Layertree with advanced features, such as thematic layersets, in three steps:

- 1. Configuration of multiple Layersets
- 2. Configuration of the map to display the Layerset
- 3. Configuration of the thematic Layertree itself

Configuration of multiple Layersets

In the example, we define two layersets with two instances each:

- Layerset Project NRW:
 - Instance NW DTK50
 - Instance Wald und Holz NRW
- Layerset World:
 - Instance OpenStreetMap (OSM)
 - Instance GEBCO

For the configuration of the layersets, the four services mentioned above were added as instances (For detailed information, see above or in the *Layerset* and *Sources* documentation).

For this example, the above mentioned steps were performed to add the Layerset "World" with the instance "OpenStreetMap (OSM)". Now we add the instance "GEBCO" in this Layerset. To use the thematic grouping, we create a new Layerset named "Project NRW" and load the two instances "NW DTK50" and "Wald und Holz NRW(Forest NRW)" into it.

The Layerset should now contain three Layersets. The **Overview** for the overview map, the **Project NRW** Layerset with two regional data sets from Western Germany and the **World**-Layerset with the supraregional data.

Configuration of the map to display the Layerset

Now, we configure the *Map element* to display the Layersets in the map. To do this, we switch to the *Layouts* tab and edit the feature in the map area. It is now important that you set an active checkbox in the Layerset "World" AND Layerset "Project NRW", so that they both appear in the application.

da	ta Layouts Layersets CSS Security			C	Q	1
Filte	r (-	ł
Ove	erview		+	\$	I	Ŵ
d	Title	Source	Туре			
32	OSM Demo	#1 OSM Demo	பீ WMS	0	¢ I	Ŵ
Рго	ject NRW		+	¢	⊡ I	Ŵ
d	Title	Source	Туре			
28	WMS Wald und Holz NRW	#7 WMS Wald und Holz NRW	ஆ wms	0	¢ I	Ŵ
29	WMS NW DTK50	#8 WMS NW DTK50	ஆ WMS	0	¢	Ŵ
Wo	rld		+	\$	I آ	Ŵ
d	Title	Source	Туре			
30	This is a WMS for the GEBCO global bathymetric grid	#9 This is a WMS for the GEBCO global bathymetric grid	ஆ WMS	0	¢	Ŵ
31	OpenStreetMap (OSM) Demo WhereGroup	#6 OpenStreetMap (OSM) Demo WhereGroup	பீ WMS	0	¢	ì

Fig. 11: Configuration of Layersets for a thematic Layertree.

If you have questions regarding further configuration of the map, you can view its configuration in the *Map element*.

Configuration of the thematic Layertree

The last step is the creation of the Layertree itself. In this example, we add the thematic Layertree to the sidepane.

If the option **Thematic layer** is disabled, the Layertree ignores the configured Layersets and shows the individual instances without thematic structuring in the main level. However, we want to show the layers of our thematic Layersets, so we activate the function **Thematic layer**. Since we inserted both Layersets into the *Map element* of the application, they are now displayed under the **Themes**-area.

Thus, to let the **themes** in the application appear as you want, there are several configuration options:

- [1] View theme If this option is set, the Layerset appears as an additional level. If this option is not set, the defined instances are displayed on the main level.
- [2] Theme open or closed If this option is set (symbol of the open folder), the theme in the Layertree is automatically opened or closed (Condition: "View theme" is also checked).

If we keep the default settings in the theme "World" and activate the other options in the theme "Project NRW", the configuration of the element will look like this:

Now we have the Layersets integrated as thematic groups. By configuring the thematic layer, the Layertree appears as follows:

The Layerset "World" is displayed as a theme, but it is closed and the two buttons are not available. In the Layerset "Project NRW" the theme is shown unfolded upon opening the application. The layers can be activated via a button.

YAML-Definition

This template can be used to insert the element into a YAML application.

title: layertree	# Title of layertree				
target: ~	# ID of the Map element to query				
type: ~	# Type of layertree (element or dialog)				
autoOpen: false	# Opens when application is started (default: false)				
<pre>showBaseSource: true</pre>	# Shows base layer (default: true)				
<pre>showHeader: true</pre>	<pre># Shows a headline which counts the number of services</pre>				
<pre>menu: [opacity,zoomtolayer,metadata,removelayer]</pre>	# show contextmenu for the layer (like opacity, zoom				
⇔to layer, metadata, remove layer), default is menu: []					
hideInfo: null					
hideSelect: null					
allowReorder					
<pre>themes: { }</pre>					

Edit element									
Title	Мар	Мар							
Layersets*	ProjectWorldOvervie	 Project NRW World Overview 							
Tile size	512								
SRS*	EPSG:3857								
Max. extent*	min x*	-20037508.342789	min y*	-20037508.342789	0				
	max x*	20037508.342789	max y*	20037508.342789					
Start extent*	min x*	772933.16	min y*	6566826.23	Ø				
	max x*	806786.66	max y*	6582317.62					
Default Resolution [dpi]*	96				0				
Fixed zoom steps									
Scales (comma- separated)*	5000000	,25000000,10000000,500	0000,1000000,	500000,100000,50000,250	000,100(
Other SRS	EPSG:258	32,EPSG:25833,EPSG:3146	56,EPSG:31467,	EPSG:4326					
Save Cancel									

Fig. 12: Configuration of Layersets for a thematic Layertree.

Edit element					
Open automat	ically 🗹 Show base sources				
Title	Layer tree				
Menu	Remove layer Opacity Zoom to layer Metadata Dimension				
🗌 Hide info 🛛 🗹	Thematic layer				
Themes	Project NRW				
	World 🗹 🖿				
✓ Allow Reorder	at TOC				
	Save Cancel				

Fig. 13: Configuration of the thematic Layertree in the map area.

🗌 Hide info	~	Thematic layer		
Themes		Project NRW	~	
		World	~	

Fig. 14: Backend configuration of the thematic layers.


Fig. 15: Configuration of the thematic Layertree in the sidepane.

3.1.7 Legend

The legend object shows a legend of the layers that are displayed in the map. Not every layer provides a legend. In addition to the legend image you can display the service title, layer name and group name (if a group exists).



Edit element						
🗹 Open automat	ically					
Title	Legend					
🗹 Show source ti	itle					
🗹 Show layer title	e					
🗹 Show grouped	layer title					
	Save Cancel					

- **Open automatically:** If activated, the legend opens when the application is started (default: active).
- **Title:** Title of the element. The title will be listed under *Layouts*. Is also shown next to the button, if "Show layer title" is activated.
- Show source title: shows WMS/source title (default: true)
- Show layer title: shows layer title (default: true)
- Show grouped layer title: shows group title for grouped layers (default: true)

The Legend element is integrated via a *Button* or in the sidepane.

Configuration Examples

Legend in the Sidepane

If you want to integrate a legend in the sidepane, click on	Ŧ	in the <i>Layouts</i> -tab (section "Sidepane").
Sidepane		0
Title Type		+

Then, choose the element "Legend" in the appearing window. The configurational dialog "Add element – Legend" will open.

Edit elem	nent					
Open automatically						
Title	Legend					
Show source ti	itle					
Show layer title	e					
🗹 Show grouped	layer title					
	Save Cancel					

Our configured element has the title "Legend". The legend opens automatically (set checkbox *Open automatically*). Moreover, the layer title and the title of all grouped layers will appear if the checkboxes *Show*

layer title and *Show grouped layer title* are set. Given this configuration, the result looks like this:



In the example the legend was added to the sidepane.

Legend in the toolbar

The legend element can be integrated with a button in the toolbar. First step: Open the application *Backend* and add the legend element into the map area section of the *Layouts* tab.

Map area

Туре

In this example, the following settings are chosen:

÷

Edit elem	ient
🗹 Open automati	cally
Title	Legend
Show source til	tle
🗹 Show layer title	
🕑 Show grouped	layer title
	Save Cancel

As soon as this element has been implemented into the map area, a *Button* has to be implemented into the toolbar section. Following these instructions, the result in the application looks like this:



The toolbar shows the button for the legend element. If the button is clicked, the dialog with the generated legend opens. With the "Open automatically" setting, the dialog is displayed directly when the application is started.

The activation and deactivation of checkboxes in the configurational settings leads to:

Edit element	Layer tree	Legend	×
C Open automatically Title Legend Show source title Show layer title Show grouped layer title Show grouped layer title	 Mapbender Users Mame i User WMS Erneuerbare Energien NRW Biomasseanlagen Deponiegas Deponiegas Dachflächenphotovoltaik Freiflächenphotovoltaik Freiflächenphotovoltaik Grubengas Klärgas Wasserkraftanlagen Windenergieanlagen 	Mapbender Users User User Unternehmen Städte, Kommunen, Kreise u.a. Privatwirtschaft WMS Erneuerbare Energien NRW Biomasseanlagen Biomasseanlagen Deponiegas Deponiegas Dachflächenphotovoltaik Ereiflächenphotovoltaik	lose
Save Cancel	Odingen		o'se

This template can be used to insert the element into a YAML application.

<pre>tooltip: 'Legend'</pre>	# text to use as tooltip
<pre>elementType: dialog</pre>	# dialog/blockelement (default: dialog)
autoOpen: true	<pre># true/false open when application is started (default: true)</pre>
displayType: list	<pre># accordion/list type of display (default: list)</pre>
target: ~	# Id of Map element to query
<pre>hideEmptyLayer: true</pre>	<pre># true/false hide when no legend is available (default: true)</pre>
<pre>showWmsTitle: true</pre>	# true/false show WMS title (default: true)
<pre>showLayerTitle: true</pre>	<pre># true/false show layer title (default: true)</pre>
<pre>showGroupedLayerTitle: true</pre>	<pre># true/false show group title for grouped layers (default: true)</pre>

You can optionally use a button to show this element. See *Button* for inherited configuration options.

3.1.8 Map

The map is the central element of a Mapbender application. It is based on OpenLayers and has be integrated into the Map area of the *Backend*.



Edit element								
Title	Мар	Мар						
Layersets*	 themes backgro overvie 	s ound themes ew						
Tile size	512							
SRS*	EPSG:385	7						
Max. extent*	min x*	-20037508.342789	min y*	-20037508.342789	8			
	max x*	20037508.342789	max y*	20037508.342789				
Start extent*	min x*	772933.16	min y*	6566826.23	0			
	max x*	806786.66	max y*	6582317.62				
Default Resolution [dpi]*	96				Θ			
Fixed zoom	steps							
Scales (comma- separated)*	5000000	5000000,25000000,10000000,5000000,1000000,500000,100000,50000,25000,100(
Other SRS	EPSG:258	32,EPSG:25833,EPSG:3146	56,EPSG:31467,	EPSG:4326				
Save Cancel								

- **Title:** Title of the element. It will be listed in the *Layouts* section.
- Layersets: Select which *Layerset* will be displayed on the map. Their order is changeable via drag & drop.

- Tile size: Size of the tiles of tiled WMS services.
- **SRS:** Spatial reference system. Two ways of SRS definitions are supported: EPSG:CODE or EPSG:CODE|MY SRS TITLE. If you do not enable a custom SRS title, the default title for each SRS from the *mb_core_srs* table is used.
- **Max. extent:** Maximal map extent, defined by BBOX parameters. This rectangle defines the possible map extent. In response to clicking the globe icon in the *Navigation Toolbar*, the map view will zoom out to this extent.
- **Start extent:** Map extent that is visible at application launch, defined by BBOX parameters. This rectangle defines the start map extent. In response to clicking the home icon in the *Navigation Toolbar*, the map view will zoom to this extent.
- **Default Resolution [dpi]**: The default resolution adapts to the screen resolution based on the configured value in dpi. Default: 96 dpi.
- **Fixed zoom steps:** This option activates a zoom behaviour with fixed scales. This is useful to increase visual quality of services that are cached on very particular resolution steps only. When set true, scale denominator snaps to one of the values given in the *scales* option as defined below (default: false).
- **Scales (csv):** A csv scale list. These scales will be supported in your application if you zoom (e.g. via mouse wheel)
- **Other SRS:** Other spatial reference systems. Two SRS definitions are supported: EPSG:CODE or EPSG:CODE|MY SRS TITLE.

Configuration example

The map element has to be included into the Map area:

Map area

Туре

The map can entail all instances that are defined in the layerset. The following example distinguishes between a *main* (1) and *overview* (2) layerset.

÷

1apbender Demo			
se data Layouts Layersets CS	S Security		U View
Filter			+
		Source	Type
21 OSM Demo		#1 OSM Demo	🔥 WMS 🛛 🗢 🏟 🗊
10 OSM Demo		#1 OSM Demo	🔥 WMS 🛛 🧔 🏟 🛍
12 OSM Demo		#2 OSM Demo	🔥 WMS 🛛 🕸 🛍
overview 2			+ 🌣 🖂 🗊
Id Title		Source	Туре
13 OSM Demo		#1 OSM Demo	🔥 WMS 🛛 🕸 🛍
			Save Cancel

In order to display all *Layersets* on the map, they have to be activated. Multiple selections are possible as well. De-selected layersets can function as an *Overview*. In the example, *main* is displayed on the main map and *overview* as an overview map.

The field *SRS* defines the coordinate reference system that is used at application start. In this example, the coordinate reference system EPSG:3857 or WGS 84/Pseudo-Mercator was chosen. If the application should support other coordinate systems, simply add those in the *Other SRS* field. In this example, the following codes are used: EPSG:25832 (ETRS89/UTM Zone 32N), EPSG:25833 (ETRS89/UTM Zone 33N), EPSG:31466 (DHDN/3-degree Gauss-Krüger Zone 2), EPSG:31467 (DHDN/3-degree Gauss-Krüger Zone 3) and EPSG:4326 (WGS 84).

The field *max*. *Extent* states the maximum zoomable extent of the map application. If there is data outside of the extent, it will not appear in the map. The field *start Extent* refers to the extent of the map that is visible when the application is started in the browser (in this example: the city of Bonn).

The *Default resolution* in dpi defines the resolution of the device being used; the corresponding default value of 96 dpi can be adjusted through this field. If the displayed resolution of the map does not match that of the WMS service, changing this value can help to align the map accordingly.

Note: The scale-dependent resolution currently only works reliably on desktops with regular resolution.

Furthermore, the field *scales (csv)* defines the scales that are usable in the application. It is possible to switch between the defined scales with *Scale Selector* or *Navigation Toolbar*. *Fixed zoom steps* were deactivated in the example. That means it is possible to display undefined zoom levels via mouse scrolling.

This template can be used to include the map into a YAML application.

```
layerset: null
                           # refer to a layerset, define the layerset first and refer to it
srs: "EPSG:4326"
                           # coordinate reference system. Two ways of srs definitions are supported:
                             - "EPSG:CODE" or
                             - "EPSG:CODE|MY SRS TITLE"
extents:
   max: [0, 40, 20, 60]
                           # maximal map extents
    start: [5, 45, 15, 55] # map extents for the start of the application
scales: "25000000,10000000,5000000,1000000,500000" # a csv scale list
otherSrs:
   - EPSG:31466
    - EPSG:31467
    - EPSG:25832
                          # other coordinate reference systems. Two srs definitions are supported:
                             - ["EPSG:CODE","EPSG:CODE"] or
                             - ["EPSG:CODE|MY SRS TITLE","EPSG:CODE|MY SRS TITLE"]
tileSize: 256
                          # size of tiles
```

Controlling URL parameters

Activating Layers

Mapbender enables the option of activating layers when an application is started via visiblelayers. Activation is possible either via *ID* or *Name*.

- ID: <InstanceID>/<InstanceLayerID>
- Name: <RootLayerName>/<LayerName>

InstanceID/InstanceLayerID: This allows a transmission of the application-specific values of InstanceID and InstanceLayerID:

?visiblelayers=<InstanceID>/<InstanceLayerID>

RootLayerName/LayerName: This allows layers along the combination of RootLayer- and LayerName to be transferred as parameters:

?visiblelayers=<RootLayerName>/<LayerName>

Hint: Please note that the IDs change after every refresh of the service. Passing the name may therefore be the more constant solution.

To display the layer properties, there is an icon with three dots next to each layer in the layerset tab of an application. Click on the icon to open a info window:

Title	Minsc	Maxsc	active	sel	ect	in	fo	tog	gle	
				allow	on	allow	on	allow	on	
Mapbender User	1	1.0							<	
Mapbender User		ID	3-1	15/4-79	Ð			-		> •
Mapbender Info	1	Layer's		apbend	der_U	lser				
		Style	def	ault					~	Ba

- **ID**: The first value in the upper text field is the internal *SourceID* and the *SourceLayerID* (3-15). The second value in the upper text field is the *InstanceID* and the *InstanceLayerID* (4-79).
- Layer's Name: The second text field contains the *LayerName*. The output of the first line will instead pass the *RootLayerName*.
- Style: Styling alternatives can be selected in the third drop-down field (if available).

For an Instance(Layer)ID transfer, use the *second* value combination after the slash for the visiblelayers parameter in the URL. Separate the two associated values with a slash (instead of a hyphen):

For example: https://localhost/mapbender/application/myapp?visiblelayers=4/79

Separate two or more non-visible layers by commas. To do this, insert the respective values according to the same scheme:

For example: https://localhost/mapbender/application/myapp?visiblelayers=4/79,1/42

Combinations of names and ID values are also possible:

https://localhost/mapbender/application/myapp?visiblelayers=Mapbender/Mapbender_Names, Mapbender/Mapbender_User,39/149

Passing POIs

You can pass coordinates with the URL. The linked position will be marked on the map using a POI (which can optionally be labelled).

- point: coordinates as comma-separated values (mandatory),
- label: Label to display (optional),
- scale: Scale to show POI in (optional).

To pass a POI, use the following URL format:

?poi[point]=368777,5619411&poi[label]=Rheinaue&poi[scale]=10000

Passing BBOX

You can pass a BBOX to zoom to by using the following URL query parameter:

?bbox=364286,5622263,365979,5622806

Passing the scale

You can set the scale from the list of available scales.

?scale=1000

Passing SRS

You can pass a favorite EPSG code you want to use on start of the application by URL query parameter:

?srs=EPSG:4326

Passing a centered Coordinate

You can pass a coordinate. The application will open and display the coordinate in the center.

?center=364286,5622263

More Start Parameters

The elements WMS Loader and WMC Loader also provide parameters you can use on start. Have a look at the element descriptions for further information.

3.1.9 Navigation Toolbar

This element is a tool to simplify navigation within the map via rotation, zoom and buttons. Different scales can be selected from a bar or slider. Users also have the option to zoom to max extent or return to the start configuration. The navigation toolbar itself can be configured to be draggable.



Add element Map area - Navigation toolbar					
Draggable					
Title	Navigation toolbar				
Components*	Rotation Zoom to maximum extent Back to start Zoom in and out Zoom slider				
Back to start	also resets layer settings				
Position*	Top left 🗸				
	Back Add Cancel				

- **Draggable:** Element is draggable or not (default: true).
- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Components:** Components of the navigation toolbal (all selected by default). Options: Rotation, Zoom to maximum extent, Back to start, Zoom in and out, Zoom slider
- "Back to start" also resets layer settings: Resets layer settings (default: false).
- **Position:** Navigation toolbar alignment, default is 'left-top' (use inline e.g. in sidebar); mandatory field. Options: inline (for using the element in the sidepane), left-top, left-bottom, right-top, right-bottom.

Note: The element must be integrated into the Map area.

Components of the Navigation Toolbar element

You can integrate various different components in the configuration dialog box. In the application these components look like this:



- **Draggable:** If you set the checkmark at draggable, a small cross will appear next to the navigation toolbar that allows the user to move the element around.
- **Rotation:** Enables changes of the map orientation. A click on the north arrow allows for a restoration of the original rotation.
- **Zoom to maximum extent:** Users can zoom to the smallest map scale by zoom to max extent. This can be set individually in the *map element*.

- Zoom to start: Restores the initial center, scale, SRS and rotation.
- **Zoom in and out:** Allows to zoom in and out of the map. The element automatically sets to the next higher or lower scale. Zoom steps can be defined in the map element as well. There, users also have the option to deactivate fixed zoom steps.
- **Zoom slider:** This component already includes *Zoom in/out*. Additionally, the user can select different scales from a bar.

This template can be used to insert the element into a YAML application.

```
tooltip: 'Navigation Toolbar'
                                 # text to use as tooltip
components: ["rotation",
                                 # components of the navigation toolbar (default: all selected)
"zoom_max", "zoom_home",
"zoom_in_out", "zoom_slider"]
target: ~
                                 # ID of Map element to query
stepsize: 50
                                 # step value for pan
stepbypixel: false
                                 # step type "by pixel"/"percent", false = percent (default: false)
anchor: left-top
                                 # navigation toolbar alignment (default: 'left-top')
                                 # use inline e.g. in sidebar
                                 # Options: 'inline', 'left-top', 'left-bottom', 'right-top', 'right-
→bottom'
draggable: true
                                 # element is draggable or not (default: true)
                                 # resets layer settings (default: false)
zoomHomeRestoresLayers: false
```

3.1.10 Overview

Mapbender provides an overview map in addition to its main map. This element can be individually adjusted in terms of size, position and zoom behaviour. The overview map refers to a specific layerset and the instance(s) it contains.



The configuration dialog offers the following settings:

Add element Map area - Overview					
Fix					
Title	Overview				
Layerset*	background themes				
Visibility*	Initially open				
Width*	200				
Height*	100				
Position*	Bottom right 🗸 🗸				
	Back Add Cancel				

- Fix: Fixes the overview extent (default: false).
- Title: Title of the element, will be listed in *Layouts*.
- Layerset: Refers to a previously defined layerset, e.g. background themes.
- **Visibility:** Initially open/Initially closed/Permanently open. Defines whether the overview will be open or closed on start. The first two options will show a button to close the overview map. The third option provides an overview map and does not show a button (Default: Initially open).
- Width: Width of the element.

- **Height:** Height of the element.
- **Position:** Position of the overview map frame in the application; options are: top left, bottom left, top right and bottom right.

Configuration examples

Edit ele	ement		
🕑 Fix			
Title	Overview		
Layerset*	overview		~
Visibility*	Initially open		~
Width*	200		
Height*	100		
Position*	Bottom right		~
			Save Cancel

The element provides various configuration options. In the example, the settings *Visibility Initially open* and *Fix* are activated. As a result, the element is displayed (i.e. maximized) when the application is opened and the view of the map is fixed. If the latter function is deactivated, the overview adapts as soon as the map is moved or the scale is changed. The start extent is displayed when the application is opened. In the example, the element has the title "Overview". It is necessary that the overview map is linked to a layerset. The following layersets are available:

↓ view + + ★ ⊠ ⊡
++ + 🌣 ビ 🛍
Type
- ype
no 🕹 WMS 🥝 🌣 🗎
no 🔥 WMS 🥝 🌣 🗊
no 🔥 WMS 🥥 🌣 🗎
+ 🌣 🗹 🗊
Туре
no 🔥 WMS 🧿 🌣 🗎
)er

In this first example, the layerset "Overview" was chosen. Width and height of the element correspond to the default setting. The position is defined as "lower right". The element looks like this in the application:



In the second example, an adjustment of the parameters (unchecking *Fix*, *Position*: left-bottom, *Width* 400 and *Height* 200) results in an overview like this:



This template can be used to insert the element into a YAML application.

<pre>tooltip: 'Overview' target: ~</pre>	# text to use as tooltip # Id of Map element to query
layerset: ~ →to it	# refer to a layerset, e.g. overview, define the layerset first and refer
width: 200	# overview width
height: 100	# overview height
<pre>anchor: 'right-top'</pre>	# overview alignment (default: 'right-top')
	# use inline e.g. in sidebar
	<pre># Options: 'inline', 'left-top', 'right-top', 'left-bottom', 'right-bottom'</pre>
visibility: open	# open/closed/open-permanent to open/closed on start will show a button to ${f D}$
\hookrightarrow close the overview map	(default: open), open-permanent will open the overview map and does not show a
-→button	
fixed: true	<pre># true/false to fix the overview extent (default: true)</pre>

3.1.11 Line/Area Ruler

The ruler is used to draw a line or area and display its length or area in a dialog. The element can be used in the sidepane or with a *Button*. Selecting a type determines whether the element measures lines or areas or whether both options are offered and the user can make the selection in the client.



Add ele	Ment Area Ruler		
Title	Line/Area Ruler		
Geometry*	line		~
Helptext	mb.core.rule	r.help	0
Line width while drawing	3		~
Style	Stroke color	rgba(51,153,204,1)	
	Stroke width (pixels)	2	
	Fill color	rgba(255,255,255,0.2)	0
	Font color	rgba(0,0,0,1)	0
	Font size	12	0
		Back Add	Cancel

- Title: Title of the element. It will be displayed in the measuring window in the application itself.
- Geometry: Choose type of element: line, area or user-selectable. Mandatory field.
- **Helptext:** Displays a help text. The default value *mb.core.ruler.help* translates to "Double-click to end drawing" (depending on the browser's display language).
- Line width while drawing: Pixel value that defines the stroke width during drawing.
- **Stroke color:** RGBA value that defines the stroke color. Can be changed using a color picker after clicking on the input field.
- Stroke width (pixels): Pixel value that defines the stroke width of the measured geometry.

- **Fill color:** RGBA value that defines the fill color of a measured area. Can be changed using a color picker after clicking on the input field. When *Line* geometry is selected, this option has no effect.
- Font color: RGBA value that defines the font color of the calculated result displayed within the geometry. Can be changed using a color picker after clicking on the input field. When *Line* geometry is selected, this option has no effect.
- Font size: Numeric value that defines the font size of the area displayed within the geometry. When *Line* geometry is selected, this option has no effect.

This template can be used to insert the element into a YAML application.

```
title: mb.core.ruler.class.title
                                             # 'Line/Area Ruler'
class: Mapbender\CoreBundle\Element\Ruler # Class of element
target: map
                                         # ID of Map element to query, e.g. 'map'
                                         # Choose type 'line', 'area' or 'both'
type: line
strokeColor: 'rgba(16, 101, 93, 0.8)'
                                         # Choose rgba value (line and area)
fillColor: rgba(100, 100, 100, 0.5)
                                         # Choose rgba value (area only)
fontColor: 'rgba(0,0,0,1)'
                                         # Choose rgba value (area only)
fontSize: 14
                                         # Choose numeric value (area only)
strokeWidth: 4
                                         # Choose pixel value (line and area)
strokeWidthWhileDrawing: 3
                                         # Choose pixel value (line and area)
```

3.1.12 Scale Bar

The Scale bar is a small line which represents the current map scale graphically.



Add elen Map area - Scale I	nent _{Dar}
Title	Scale bar
Maximum width*	200
Unit*	kilometer 🗸
Position*	Bottom right 🗸
	Back Add Cancel

- **Title:** Title of the element. It will be listed under *Layouts*.
- Maximum width: The maximum width of the scale bar (mandatory field; default: 200px).
- Unit: Scale bar units 'kilometer' or 'miles' (mandatory field; default: kilometer).
- Position: Scale bar alignment (mandatory field; default: Bottom right).

This template can be used to insert the element into a YAML application.

tooltip: 'Scale Bar'	# text to use as tooltip
target: ~	# ID of the Map element to query
<pre>anchor: 'inline'/'left-top'/</pre>	<pre># scale bar alignment (default:'right-bottom')</pre>
<pre>'left-bottom'/'right-top'/</pre>	# use inline, e.g. in sidebar
'right-bottom'	
<pre>position: ['10px', '10px']</pre>	# scale bar position (default:x=20px, y=20px)
maxWidth: 200	# the maximum width of the scale bar (default: 200px)
<pre>units: ['km']</pre>	<pre># scale bar units 'kilometer' and/or 'miles' (ml) (default: ['km'])</pre>

3.1.13 Scale Display

The Scale Display shows the current map scale (e.g. as 1:7,500 or 1:10K).



Add elem	isplay	
Title	Scale display	
Prefix	mb.core.scaledisplay.label	0
Shorten scale		0
Position*	Bottom right	~
	Back Add	Cancel

- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons.
- **Prefix:** Customizable description shown before the actual scale. The default mb.core. scaledisplay.label is rendered as *Scale* in the user's language.
- **Shorten scale:** If checked, scale numbers from 10,000 or higher will be shortened with a postpositioned K or M (e.g. 10,000 as 10K).
- **Position:** Scale display alignment (mandatory field; default: 'Bottom right').

This template can be used to insert the element into a YAML application.

<pre>tooltip: 'ScaleDisplay'</pre>	# text to use as tooltip
target: ~	# ID of Map element to query
<pre>anchor: 'inline'/'left-top'/</pre>	<pre># Scale Display alignment, default is 'right-bottom'</pre>
<pre>'left-bottom'/'right-top'/</pre>	# use inline, e.g. in sidebar
'right-bottom'	
<pre>scalePrefix: Scale</pre>	# prefix, shown with scale
unitPrefix: false	# prefix, shown with unit, e.g. 1000 as 1K

3.1.14 Scale Selector

This element displays a selectbox with scales. The map scale changes when a different value from the selectbox is chosen. The selectbox only offers scales that have been defined in the map element.



Add elem	ient elector
Show label	
Title	Scale selector
Tooltip	mb.core.scaleselector.class.title
	Back Add Cancel

- Show label: Displays label of the Scale Selector (default: false).
- **Title:** Title of the element. The title will be listed under *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Tooltip:** Text to use as tooltip.

This template can be used to insert the element into a YAML application.

tooltip: "Scale selector" # text to use as tooltip
target: ~ # Id of Map element to query
label: false # false/true to label the scale selector (default: false)

3.1.15 SRS Selector

The spatial reference system selector changes the map's spatial reference system. The selectbox offers SRS that are defined within the *Map element*.



Add elem	ient tor
Show label	
Title	SRS selector
Tooltip	mb.core.srsselector.class.title
	Back Add Cancel

- Show label: Labels the SRS Selector (default: false).
- **Title:** Title of the element. The title will be listed under *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Tooltip:** Text to use as tooltip.

This template can be used to insert the element into a YAML application.

```
tooltip: 'SRS Selector' # text to use as tooltip
label: false # true/false to label the SRS Selector (default: false)
target: ~ # Id of the Map element to query
```

3.2 Editing

3.2.1 Digitizer

The digitizer element allows the creation and editing of points, lines and areas on a map. In contrast to sketch, this element saves geometries in a table in a database. Currently Mapbender supports Post-greSQL. SpatiaLite and Oracle are available experimentally. Development was carried out in a way that digitizer can be extended to include other data sources such as OGC WFS as well.

In order to use the digitizer, one has to define a specific yaml-definition:

Setting up of Digitizer

You can only use the element in the sidepane.

Eleme	ent editieren	8
Tistes		
Diett		
Digitize	er	
Target		
Main N	Мар	~
Scheme	85	
1	poi:	^
2	label: 'point digitizing'	
З	inlineSearch: true	
4	maxResults: 500	
5	featureType:	
6	connection: gisdb	
7	table: punkt	
8	uniqueId: gid	
9	geomType: point	
10	geomField: geom	
11	srid: 4326	
12	openFormAfterEdit: true	
13	zoomScaleDenominator: 500	
14	allowEditData: true	
15	allowDelete: true	
16	allowDigitize: true	
17	useContextMenu: true	
18	toolset:	
19	•	~

- **Title:** Title of the element. This is displayed in the layouts list and allows you to define several elements.
- Target: (ID) of the map.

• Schemes: YAML-Definition of the element Digitizer

The Ditigitzer needs access to a database where the editable tables are. You have to define a new database configuration to be able to connect with the geo database. Read more about this under YAML Configuration (Configuration and Application files).

The definition of the Digitizer is done in YAML syntax in the textarea configuration at schemes. Here you define the database connection, the editable table, the form to display the table, the attribute form and other behavior.

Hint: If errors occur in the database, fields or form, various error messages will appear. Here, the productive environment will only give a general error message. If you want to see the exact error, you should call the page as development environment. Find more under en/quickstart:Start Mapbender in a productive environment.

• debug: Display error messages, e.g. syntax error in SQL [experimental]

```
poi:
    [...]
    debug: true
    [...]
```

YAML-Definition for the element Digitizer in the textarea schemes

In the following YAML block, the example definition for three Digitizer forms is included. Copy the following block into your Digitizer element to test the capture of points, lines, and polygons. You must first create the database connection and the three demo tables. The SQL commands for creating the tables can be found below. The functionality of the built-in features and additional functions are explained in more detail in this example.

```
poi:
    label: point digitizing
    inlineSearch: true
    featureType:
        connection: search_db
        table: poi
        uniqueId: gid
        geomType: point
        geomField: geom
        srid: 4326
    openFormAfterEdit: true
    zoomScaleDenominator: 500
    allowEdit: true
    allowDelete: true
    allowDigitize: true
   useContextMenu: true
    toolset:
        - type: drawPoint
        - type: moveFeature
    popup:
        title: point test suite
        width: 500px
    searchType: currentExtent
    tableFields:
```

(continues on next page)

(continued from previous page)

```
gid: {label: Nr. , width: 20%}
   name: {label: Name , width: 80%}
styles:
    default:
        strokeWidth: 2
        strokeColor: '#0e6a9e'
        fillColor: '#1289CD'
        fillOpacity: 1
        fillWidth: 2
        pointRadius: 10
    select:
        strokeWidth: 3
        strokeColor: '#0e6a9e'
        fillOpacity: 0.7
        pointRadius: 10
formItems:
   - type: tabs
     children:
       - type: form
         title: Basic information
         css: {padding: 10px}
         children:
             - type: label
               title: Welcome to the digitize demo. Try the new Mapbender feature!
             - type: input
               title: Name
               mandatory: true
               name: name
               mandatoryText: Please give a name to the poi.
               infoText: "Help: Please give a name to the new object."
             - type: input
               title: Title
               mandatory: false
               name: title
               mandatoryText: Please give a title to the poi.
             - type: textArea
               name: abstract
               title: Abstract
               placeholder: 'please edit this field'
             - type: select
               title: Type
               name: type
               options: {A: A, B: B, C: C, D: D, E: E}
             - type: breakLine
       - type: form
         title: Personal information
         css: {padding: 10px}
         children:
             - type: label
               title: Please give us some information about yourself.
             - type: fieldSet
               children:
                   - type: input
                     title: Firstname
                     name: firstname
                     css: {width: 30%}
```

(continues on next page)
```
- type: input
                         title: Lastname
                         name: lastname
                         css: {width: 30%}
                       - type: input
                         title: E-Mail
                         name: email
                         css: {width: 40%}
                 - type: select
                   multiple: false
                   title: Interests
                   name: interests
                   options: {maps: maps, reading: reading, swimming: swimming, dancing: dancing, beer:
→beer, flowers: flowers}
                 - type: date
                   title: favorite Date
                   name: date_favorite
                   mandatory: true
                   css: {width: 25%}
                 - type: breakLine
                 - type: breakLine
                 - type: checkbox
                   name: public
                   value: true
                   title: public (this new object is public)
line:
    label: line digitizing
    inlineSearch: true
   featureType:
        connection: search_db
        table: lines
        uniqueId: gid
        geomType: line
        geomField: geom
        srid: 4326
    openFormAfterEdit: true
    allowDelete: true
    useContextMenu: true
    toolset:
        - type: drawLine
        - type: modifyFeature
        - type: moveFeature
    popup:
        title: line test suite
        width: 500px
    searchType: currentExtent
    tableFields:
        gid: {label: Nr. , width: 20%}
        name: {label: Name , width: 80%}
    styles:
        default:
            strokeWidth: 2
            strokeColor: '#0e6a9e'
            fillColor: '#1289CD'
            fillOpacity: 1
            fillWidth: 2
```

(continues on next page)

```
pointRadius: 10
        select:
            strokeWidth: 3
            strokeColor: '#0e6a9e'
            fillOpacity: 0.7
            pointRadius: 10
    formItems:
       - type: form
         title: Basic information
         css: {padding: 10px}
         children:
             - type: label
               title: Welcome to the digitize demo. Try the new Mapbender feature!
             - type: input
               title: Name
               name: name
               mandatory: true
               mandatoryText: Please give a name to the new object.
               infoText: "Help: Please give a name to the new object."
             - type: select
               title: Type
               name: type
               options: {A: A, B: B, C: C, D: D, E: E}
polygon:
   label: polygon digitizing
    inlineSearch: true
    featureType:
        connection: search_db
        table: polygons
        uniqueId: gid
        geomType: polygon
        geomField: geom
        srid: 4326
   openFormAfterEdit: true
    allowDelete: false
    useContextMenu: true
    toolset:
       - type: drawPolygon
        - type: drawRectangle
        - type: drawDonut
        - type: drawEllipse
        - type: drawCircle
        - type: modifyFeature
        - type: moveFeature
    popup:
        title: polygon test suite
        width: 500px
    searchType: currentExtent
   tableFields:
        gid: {label: Nr. , width: 20%}
        name: {label: Name , width: 80%}
    styles:
        default:
            strokeWidth: 2
            strokeColor: '#0e6a9e'
            fillColor: '#1289CD'
```

(continues on next page)

fillOpacity: 1	
fillWidth: 2	
pointRadius: 10	
select:	
strokeWidth: 3	
strokeColor: '#0e6a9e'	
fillOpacity: 0.7	
pointRadius: 10	
formItems:	
- type: form	
title: Basic information	
css: {padding: 10px}	
children:	
- type: label	
title: Welcome to the digitize demo. Try the new Mapbender feature!	
- type: input	
title: Name	
mandatory: true	
name: name	
mandatoryText: Please give a name to the new object.	
infoText: "Help: Please give a name to the new object."	
- type: select	
title: Type	
name: type	
options: {A: A, B: B, C: C, D: D, E: E}	

SQL for the demo tables

The following SQL commands must be executed in your database. You create three demo tables so that the individual functions can be tested using the YAML definition shown above.

```
create table public.poi (
   gid serial PRIMARY KEY,
   name varchar,
   type varchar,
   abstract varchar,
   public boolean,
   date_favorite date,
   title varchar,
   firstname varchar,
   lastname varchar,
   email varchar,
   interests varchar,
   user_name varchar,
   group_name varchar,
   modification_date date,
   my_type varchar,
   file_reference varchar,
   x float,
   y float,
   city varchar,
   geom geometry(point,4326)
);
```

create table public.lines (gid serial PRIMARY KEY, name varchar, type varchar, abstract varchar, public boolean, date_favorite date, title varchar, firstname varchar, lastname varchar, email varchar, interests varchar, length float, category varchar, user_name varchar, group_name varchar, modification_date date, my_type varchar, file_reference varchar, x float, y float, city varchar, geom geometry(linestring,4326));

create table public.polygons (gid serial PRIMARY KEY, name varchar, type varchar, abstract varchar, public boolean, date_favorite date, title varchar, firstname varchar, lastname varchar, email varchar, interests varchar, area **float**, category varchar, user_name varchar, group_name varchar, modification_date date, my_type varchar, file_reference varchar, x float, y **float**, city varchar, geom geometry(polygon,4326)

);

Configuration

The following chapters explain the individual components of the Digitizer that build up the base-structure and which can be used in the formular.

Feature basic definition

A basic definition, here for the poi-example, may look like the following snippet:

```
poi:
    label: point digitizing
   minScale: 5000
    featureType:
        connection: search db
        table: poi
        uniqueId: gid
        geomType: point
        geomField: geom
        srid: 4326
        filter: interests = 'maps'
   openFormAfterEdit: true
    zoomScaleDenominator: 500
    allowEdit: true
    allowDelete: true
   allowDigitize: true
    [...]
    popup:
        [...]
```

The possible options are:

- label: Label of the Digitizer popup
- **minScale:** Minimum scale, where the features should be displayed in the map (e.g. minscale: 5000 = show from a scale 'over' 1:5000, when zooming out).
- featureType: Connection to the database
 - connection: Name of the database-connection from the parameters/doctrine.yaml
 - table: Table-name in which the FeatureTypes are stored
 - uniqueId: Column-name with the unique identifier
 - geomType: Geometry-type
 - geomField: Column-name in which the geometry is stored
 - srid: Coordinate-system in EPSG-code
 - filter: Data filters for values in a defined column, e.g. filter: interests = 'maps'
- **openFormAfterEdit:** After creating a geometry the form popup is opened automatically to insert the attribute data (default: true)
- **zoomScaleDenominator:** Zoom-scales to use for zooming to a feature.
- **allowEdit:** Allow to edit form data and save geometries [true/false]. allowDigitize decides whether the geometry may be edited.

- **allowDigitize:** Allow to edit geometries, e.g. moving the entire geometry, adding support points to polygons, etc. [true/false]. If true, the digitizing buttons appear (new point, move, etc.). Only evaludated if allowEdit is set to true.
- **allowDelete:** Allow to delete data [true/false]. The Delete button is always visible.
- useContextMenu: Show the context-menu of a feature. [true/false]
- allowCancelButton: Show the Cancel button [true/false]. See Save, Delete, Cancel.
- allowDeleteByCancelNewGeometry: If true: When you create a new feature, the Cancel button will behave like the Delete button: The feature is removed from the map and the table. This is not the case if you edit an existing feature. [true/false]
- **displayOnInactive:** The current FeatureType will still be displayed on the map, although the Digitizer is deactivated in the Sidepane (Accordion, Tabs) [true/false]. If switched to true, this option is a bit tricky, due to the still activated Digitizer events but will be helpful for experienced users.
- **allowLocate:** Navigation to a feature via the tabs-keyboard-button, simple for operation without mouse. [True / false]. An extra "zoomTo" Button is displayed for each feature.

Nr.	JΞ	Name	÷	
2		А	• •	2 ×
7		as	÷.	2 ×
8		asdas	• 1	≥ ×
9		afgagaga	• 1	≥ ×

• **allowChangeVisibility:** Allow to change the visibility of one feature in the map (visible / invisible). [true/false]. An Eye Symbol is displayed, which allows to hide or display each feature individually.

Nr.	損	Name 🗢				
2		Α	φ	Ð	٢	×
7		as	¢	B	٢	×
8		asdas	¢	B	٢	×

• **showVisibilityNavigation:** Allow to change the visibility of all features in the map (visible / invisible). [true/false]

point digitizing				
8 75 4	∕ØAlle ausblenden	∕©Alle einblenden		

Experimental:

• **allowCustomerStyle:** Allow user-specific styles for features in the map [true/false]. This feature is experimental: For each feature you can set unique styles.

point digitizing			
of 75 拜	ø Alle ausblenden	©Alle einblenden	

A style-manager is used to let you set the unique styles.

Fullung Rand Beschriftung Farbe Deckkraft 1 Punkt Radius 10 #1289cd Image: Contract 1 Punkt Radius 10 #1289cd Image: Contract 1 Breite 2 #d23e00 Image: Contract 2 Image: Contract 2 Fullung Rand Beschriftung Grösse Image: Contract 2 Image: Contract 2 Fontname Image: Contract 2 Image: Contract 2 Forther Image: Contract 2 Image: Contract	Stylema	anager					
Farbe Deckkraft 1 Punkt Radius 10 #1289cd Aktivieren Aktivieren Foilung Rand Beschriftung Style abgerundet Durchgezogen Aktivieren Aktivieren Style abgerundet Durchgezogen Aktivieren Biologic Ait Operation (Contraction (Füllung	Rand	Beschriftung				
#1289cd Aktivieren Abbrechen Speichern Stylemanager #d23e00 Glättung style abgerundet V Durchgezogen Aktivieren Aktivieren Stylemanager Füllung Rand Beschriftung Stylemanager Füllung Rand Beschriftung Image: Stylemanager Füllung Rand Beschriftung Image: Stylemanager Füllung Rand Beschriftung Image: Stylemanager Füllung Rand Beschriftung Image: Stylemanager Fürber Image: Stylemanager Image: Stylemanager Stylemanager Image: Stylemanager <td>Farbe</td> <td></td> <td>Deckkr</td> <td>aft 1</td> <td></td> <td>Punkt Radius 1</td> <td>10</td>	Farbe		Deckkr	aft 1		Punkt Radius 1	10
Aktivieren Abbrechen Stylemanager Farbe Deckkraft 1 Breite 2 #d23e00 Glättung abgerundet Durchgezogen Aktivieren Abbrechen Style abgerundet Durchgezogen Abbrechen Style abgerundet Durchgezogen Abbrechen Stylemanager Füllung Rand Beschriftung Image: Comparison of the second o	#1289cd						
Abbrechen Speichern Stylemanager Style Farbe Deckkraft 1 Breite 2 #d23e00 Glättung abgerundet • Durchgezogen • Aktivieren Stylemanager Füllung Rand Beschriftung • • Aktivieren • <t< td=""><td>Aktivi</td><td>eren</td><td></td><td></td><td></td><td></td><td></td></t<>	Aktivi	eren					
Stylemanager Füllung Rand Beschriftung Farbe #d23e00 Glättung abgerundet Durchgezogen Aktivieren Abbrechen Stylemanager Füllung Rand Beschriftung Grösse ① Arial, Helvetica, sans-serif Intervent Fontname ① Grösse ② Art ③ Farbe Pockkraft 1						Abbrechen	Speichern
Füllung Rand Beschriftung Farbe Deckkraft 1 Breite 2 #d23e00 Image: Constraint of the second se	Stylema	anager					國本業
Farbe Deckkraft 1 Breite 2 #d23e00 Style Glättung Style abgerundet Durchgezogen Øktivieren Aktivieren Stylemanager Füllung Rand Beschriftung Grösse (a) Arial, Helvetica, sans-serif Indication Farbe Deckkraft 1	Füllung	Rand	Beschriftung				
#d23e00 Glättung abgerundet Durchgezogen Aktivieren Abbrechen Speichern Stylemanager Füllung Rand Beschriftung Fontname () Arial, Helvetica, sans-serif Indiant Protect () Farbe Deckkraft 1	Farbe		Deckkr	afit 1		Breite 2	
Glättung abgerundet	#d23e00						
abgerundet Durchgezogen Aktivieren Abbrechen Speichern Stylemanager Füllung Rand Beschriftung Fontname Grösse Art In Normal Farbe Deckkraft 1	Glättung				Style		
Aktivieren Abbrechen Speichern Stylemanager Füllung Rand Beschriftung Fontname () Arial, Helvetica, sans-serif Interve Beckkraft 1 #000000	abgerun	det		-	Durchgezog	gen	-
Stylemanager Füllung Rand Beschriftung Fontname I Arial, Helvetica, sans-serif Intervention Farbe Beckkraft 1 Pontname I	AKUVI	eren				Abbrechen	Speichern
Füllung Rand Beschriftung Fontname Grösse Art Arial, Helvetica, sans-serif 11 Normal Farbe Deckkraft 1 #000000	Stylem	anager					國本業
Fontname Arial, Helvetica, sans-serif Farbe #000000	Füllung	Rand	Beschriftung				
Fontname () Arial, Helvetica, sans-serif Farbe #000000		(Elegenes)					6
Fontname () Grösse () Art () Arial, Helvetica, sans-serif () 11 () Normal () Farbe Deckkraft 1 #000000							
Fontname Grösse Art Arial, Helvetica, sans-serif 11 Normal Farbe Deckkraft 1							
Farbe Deckkraft 1	Fontnam	ie ()		_	Grösse 🕄	Art 🕥	-
#000000	Earbe	ervetica, s	ans-sent		Deckkraft 1		
	#000000)					
Abbrechen Speichern						Abbrechen	Speichern
	16	10				1-	
Prezence -	Freia Rhe	noue	0		200		

Definition of the popup

Digitizer post dguing • Sets try cover steret only • Sets try cover steret only • • • • • • • • • • • • • • • • • • •	Mapbender		Mapbender Digitize Demo	🚯 FeatureInfo 🖨 🙆 📰 🛇 🎋 🍫
Import degrade Import degr	Digitizer			
 Security current extent only ■ ■ ■	point digitizing V			
Image: Image	Select by current extent only	P	oint test suite	*
All we must be formed. Image: Provide the degrade demo. Try the new Mapbender feature! Nume 0 1 1 1	1 · · · · · · · · · · · · · · · · · · ·	Bas	sic information Personal information	internation of the second seco
Lin 1 1 2 3 1 2 3 1 2 2 </td <td>ilter:</td> <td>Ampel</td> <td>leicome to the digitize demo. Try the new Mapbender feature!</td> <td>In the second seco</td>	ilter:	Ampel	leicome to the digitize demo. Try the new Mapbender feature!	In the second seco
Image: Second Provide Provi		No	ame 🕀 🗓	L'ELE
i kernedybrucks i kernedybrucks i i <t< td=""><td>l≛ Nr. ≑ Name</td><td></td><td>Baum</td><td></td></t<>	l≛ Nr. ≑ Name		Baum	
2 Uni 3 Rheinufer 4 Baum 6 O C C C 5 Baum 6 O C C C 5 Baum 1 C C C C C C C C C C C C C C C C C C C	1 Kennedybrücke 🖓 👁 🕼 🗎 🗙		itle	
Baum Baum Baum Baum Baum Baum Correct Baum Baum <td>2. Uni 🛃 👁 🖬 🗙</td> <td></td> <td>Baum</td> <td></td>	2. Uni 🛃 👁 🖬 🗙		Baum	
Baum Deliver 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2	Rheinufer 🔁 👁 🖻 😑 🗙	A	bstract	
Showing 1 to 5 from 8 1 2 • • • • • • • • • • • • • • • • • •	Baum 🔮 👁 🖻 🗙		MADS	
Showing 1 to 5 from 8 Type 0 B Mapbender user/group User: root group:ROLE_USER Text with function type:text User: root group:- Layer tree Sketches Search router Type 0 B Mapbender user/group User: root group:- Defender user: root group:	Baum			
1 2 Type 0 B Mapbender user/group User: root group:Rolle_USER Text with function type:text User: root group: Copy: Save Delete Cancel Veststadt Substant Sketches Finant Search router Finant	Showing 1 to 5 from 8			
B Mapbender user/group user: root group.ROLE, USER Text with function type:text user: root group Copy Save Delete Cancel Verstradt Sketches Search router Ungelet & Context, Pelago, Policy Over, re-	1 2	Ту	уре Ө	
Layer tree Sketches Search router		Baum Baum	В	
Layer tree Sketches Search router		Baum		
Layer tree Sketches Search router Unrefet & Contact, PelipacePolicy		aum III	rappender user/group	
Layer tree Sketches Search router TESSI / ITM more 32N TESSI /		Tr	ext with function type:text	
Layer tree Sketches Search router TESSI / ITM more 32N TESSI /		us	ser: root group: -	
Layer tree Sketches Search router Descript & Control				
Layer tree Sketches Search router Institut for the second			Copy Save Delete	Cancel
Sketches Search router Image & Contact, Reliance Policy, Art, and	Layer tree			Südstadt
Search router	Sketches			
Imprint & Contact, Privacy, Pr	Search router			Poppelsdorf
imprint de contact i intracy i one y i i i i i i i i i i i i i i i i i i	Imprint & Contact Privacy-Policy 💠 x: - y:	ETRS89 / UTM	zone 32N 🗸 1445 🗸 Mapbender Digitize Demo	© OpenStreetMap contributors powered by Mapben

In connection with the digitization, very complex forms can be generated for the acquisition of data.

The following option for the construction of the forms are available:

- Define more than one feature type for digitization. You can switch from one feature type to another with a select box.
- It is possible to define a filter to only query a subset of your database table.
- Textfields
- Selectboxes, Multiselectboxes
- Checkboxes and Radiobuttons
- Textareas
- Datepicker
- File upload and Image Display
- Definition of tabs
- Definition breakLines
- Definition of Text
- Mandatory fields, regular expressions to validate the field input
- Definition of help texts
- Refresh after save
- Possibility to copy entered information from a form into the clipboard via a button

			X
point test suite			× `
Basic information	Personal information		
Welcome to the digit	tize demo. Try the new Manhende	r festurel	
welcome to the digit	ize demo. Try the new mapbende	ricature:	
Name 🤁 🖺			_
Baum			
Title			
Baum			75
Abstract			
MAPS			
			10
Туре			
В		· · · · · · · · · · · · · · · · · · ·	
Mapbender user/g	roup		
user: root group:ROI	LE_USER		
Text with function	type:text		-51
user: root group: -			
	Cor	y Save Delete Cancel	
pup: experimental adaptati	ons bere: http://ani_iqueryui_c	# Define the form as a	popup. Further
title: POI		# Definition of the po	oup title
height: 400 width: 500		# height of the popup # width of the popup	
#modal · true		# Everything excent th	e form window i
grayed out and the po	sition and size of the window i	s fixed for the duration of the	data collection
#position: {at: "le <u></u> area	ft+20px", my: "left top-460px"	} # Position of the popu	p in the browse

Definition of the feature table

The Digitizer provides an object table. It can be used to navigate to features (zoom on the objects) and open the editing form. The object table can be sorted. The width of the individual columns can optionally be specified in percent or pixels.

- tableFields: define the columns for the feature table.
 - definition of a colum: [table column]: {label: [label text], width: [css-definition, like width]}
- **searchType:** search extent in the map, display of all features in the result table or only features displayed in the current extent [all / currentExtent] (default: currentExtent).
- **showExtendSearchSwitch:** Activate or deactivate the display of the searchType selectbox for searching in the curret extent [true/false]
- view: Settings for the object result table
 - type: Templatename [table]
 - settings: Settings for the functions of the result table (Newly added, not fully documented!)

You can find more detailed information on possible configurations under https://datatables.net/ reference/option/.

```
searchType: currentExtent
showExtendSearchSwitch: true
tableFields:
    gid: {label: Nr. , width: 20%}
    name: {label: Name , width: 80%}
view:
    type: table
    settings:
        info: true
        processing: false
        ordering: true
        paging: true
        selectable: false
        autoWidth: false
        order: [[1, "asc"]] # 1 / 2 presort columns
```

Tabs (type tabs)

Form elements can be placed unto different Tabs. The formItem type "tabs" is used for this.

```
formItems:
   - type: tabs
                                                                     # Type tabs creates tabs in the popup
     children:
                                                                     # The tabs are defined as sub-objects
\rightarrow (children) of the form.
       - type: form
         title: Basic information
                                                                     # title of the tabs
         css: {padding: 10px}
         children:
                                                                     # Multiple subobjects in groups can be
\leftrightarrowused to arrange data in the form next to each other
              - type: label
                title: Welcome to the digitize demo. Try the new Mapbender feature!
                . . .
```

For each input field the CSS-behavior and styling information can be assigned, regardless of the type. This can be used, for example, to highlight important fields or to fill an attribute field when editing another field.

parameters:

- load, focus, blur
- input, change, paste
- click, dblclick, contextmenu
- keydown, keypress, keyup
- dragstart, ondrag, dragover, drop
- mousedown, mouseenter, mouseleave, mousemove, mouseout, mouseover, mouseup
- touchstart, touchmove, touchend, touchcancel

```
formItems:
   - type: tabs
    children:
       - type: form
         [...]
              type: input
               name: firstname
               title: Firstname
               css: {width: 30%}
               input: |
                    var inputField = el;
                    var form = inputField.closest(".modal-body");
                    var datenkennungField = form.find("[name='datenkennung']");
                    datenkennungField.val(inputField.val());
               focus: |
                    var inputField = el;
                    var form = inputField.closest(".modal-body");
                    form.css("background-color","#ffc0c0");
               blur: |
                    var inputField = el;
                    var form = inputField.closest(".modal-body");
                    form.css("background-color","transparent");
             - type: date
               name: date
               title: Date
               css: {width: 30%}
               # Highlight the year if you edit the date-field and autom. insert the year from the date
               change: |
                    var inputField = el;
                    var form = inputField.closest(".modal-body");
                    var yearField = form.find("[name='year']");
                    var year = inputField.val().match(/\d+$/)[0];
                    yearField.val(year);
                    yearField.css("background-color","#ffc0c0");
```

Text fields (type input)

- type: input	# element type definition
title: Title for the field	# labeling (optional)
<pre>name: column_name</pre>	<pre># reference to table column (optional)</pre>
copyClipboard: false	<pre># true/false. if true, specify a button that copies</pre>
\hookrightarrow entered information to the clipboard (default: f	false) (optional)
mandatory: true	# specify mandatory field (optional)
<pre>mandatoryText: You have to provide information.</pre>	<pre># text occurs if the column is empty on save</pre>
cssClass: 'input-css'	# css class to use as style for the input field
⇔(optional)	
value: 'default Text'	# define a default value (optional)
<pre>placeholder: 'please edit this field'</pre>	# placeholder appears in the field as information
→(optional)	

Selectbox (selectbox or multiselect [type select])

By defining a selectbox, predefined values can be used in the form. You can choose between a selectbox with a selectable entry (type select) or a multiselectbox with several selectable entries (type multiselect).

(1) select - one selectable entry

- type: select	<pre># element type definition</pre>	
<pre>title: select a type</pre>	<pre># labeling (optional)</pre>	
<pre>name: my_type</pre>	<pre># reference to table column (optional)</pre>	
copyClipboard: false	# specify button that copies chosen values to the clipboard $\!$	
↔(optional). [true/false]	(default: false).	
<pre>multiple: false</pre>	# define a multiselect (default: false)	
options:	<pre># definition of the options (key, value)</pre>	
1 : pub		
2: bar		
3: pool		
4: garden		
5: playground		

(2) multiselect - several selectable entries

The Multiselect-Box is activated by the attribute "multiple: true". You can choose multiple entries in the selectbox. The usage and their requirements of the database may vary. In general with the example above, you can switch the "interests" in the POIs to multiselects. The database fields is still a character varying.

```
type: select
multiple: true
title: Interests
name: interests
copyClipboard: false
options:
    maps: maps
    reading: reading
    swimming: swimming
    dancing: dancing
    beer: beer
    flowers: flowers
```

Notes: From Digitizer version 1.2 and up, the multiple selection provides an easier mechanism to choose an entry, which also allows a search in the drop-down-list. The navigation through the list is possible via keyboard. Possible entries are highlighted during typing. An already chosen entry can be removed by clicking the small "x" symbol. Check up-to-date information about digitizer versions: https://github.com/mapbender/mapbender-digitizer

point test suite		22 个 🗙
Basic information	Personal information	
Please give us som Firstname	e information about yourself. Lastname	E-Mail
John	Doe	john.doe@wheregroup.com
Wählen Sie einen 1	ſyp aus	
×Prof. ×Dr.		
Prof.		
Dr.		
med.		
jur.		
vet.	\$	Abbrechen
habil		

The SQL (if maps and reading were chosen):

```
gisdb=> select interests from poi where gid=3;
interests
.....
maps,reading
(1 row)
```

The keywords are saved in the database (for example: "dancing: Tanzen" and "flowers: Blumen" stores "dancing, flowers"). It is possible to copy several values to the clipboard with CopyClipboard: true.

Get the options for the selectbox via SQL

With a SQL request, the values of the selectbox can be directly pulled from the database. In this case, the key value mapping is not possible and only the indices of the entries can be stored.

Text/Label (type label)

Text (type text)

Texts can be defined as a label in the form. In this case, fields of the data source can be accessed by using JavaScript.

Textareas (type textarea)

Similar to the text field via type input (see above), text areas can be created that can contain several lines using type textArea.

- type: textArea	# Typ textArea creates a text area
rows: 4	# Number of rows for the text area that appears when the form is \square
\hookrightarrow opened. Field can be expanded by	mouse in the form.
<pre>name: beschreibung</pre>	# table column
title: Bestandsaufnahme Bemerkung	# Label (optional)

Breaklines (type breakLine)

- type: breakLine

element type definition, will draw a line

Checkboxes (type checkbox)

```
    type: checkbox # Type checkbox creates a checkbox. When activated, the specified value (here
        'TRUE') is written to the database.
        title: Is this true? # Label (optional)
        name: public # table column
        value: true # parameter when activating the checkbox is stored in DB (here 'TRUE').
        checked: false # [true/false] behaviour of the checkbox (default: false). Defines whether[]
        → checkbox is pre-selected (checked) on load
```

Mandatory fields

The notes for a mandatory field appear above the used fields. In the case of a missing entry in a defined mandatory field, this will be marked in red and (if defined) a speech bubble will appear. The object can not be saved if mandatory data is missing.

Note: When using multiple tabs in the form, the creator may set an entry incorrectly on a non-visible tab in a mandatory field, so the saving process does not work. No error message appears outside the form. The applicant has to check the information in the form (label: red border/speech bubble with reference) before it can be stored correctly.

```
- type: [Angabe zum Feldtyp]
                                        # Each field can be made mandatory
 mandatory: true
                                        # true - field has to be set. Else you can't save the object.
→Regular expressions are possible too - see below.
 mandatorytitle: Mandatory info!
                                       # Text that appears in the field when the field is not filled \Box
\leftrightarrow or filled with an invalid value.
 mandatoryText: Please choose a type! # Text that is displayed in a speech bubble above the field
\rightarrow when the field is not filled when it is saved or invalid.
 mandatory: /^\w+$/gi
                                        # You can define a regular expression to check the input for a
→field. You can check e.g. for email or numbers. Read more http://wiki.selfhtml.org/wiki/JavaScript/
→ Objekte/RegExp
 # Check if input is a number
 mandatory: /^[0-9]+$/
 mandatoryText: Only numbers are valid for this field!
```

Date-picker (type date)

	favori 1988	te D	ate					
	<	Ma	ay T	2	015	•	>	
	4	5	6	7	1 8	2	3 10	-/
	11 18	12 19	13 20	14 21	15 22	16 23	17 24	
	25	26	27	28	29	30	31	
-	type: title name:	dat : fa dat	e ivor :e_f	ite avor	Date	9		

Helptexts to the form-elements (attribute infotext)

The infotext can appear over every field, regardless of whether this is a mandatory field or not. If a infotext is specified, an info button appears above the field. Clicking on this button opens the information text.

```
- type: [type name]  # every field, regardless of whether□

→ this is a mandatory field or not

infoText: Please note - only numbers are valid for this field. # Notice which will be displayed by i-
→ symbol
```

Element groups (type: fieldSet)

Elements can be grouped together in one row to provide logical connections or save space. To define a group you have to set type fieldSet and afterwards define the children which shall be grouped.

For each children you can define a width to control the pace for each element.

(continues on next page)

title: E-Mail
name: email
css: {width: 40%}

Coordinate Fields (type coordinates)

For visual verification, manual entry or manual editing of point coordinates, the *coordinates* element can be used.

EPSG angeben	Latitude:	Longitude:
EPSG:3857 (Pseudo Mercator)	6142784.4091751	1553813.9524897

-	type: coordinates
	title_epsg: 'EPSG angeben'
	title_longitude: 'Longitude'
	title_latitude: 'Latitude'
	<pre>coordinatesFieldsOrder: ['epsg','x','y']</pre>
	title: ''
	css: {width: 100% }
	<pre>epsgCodes: [['EPSG:3857', 'EPSG:3857 (Pseudo Mercator)'], ['EPSG:4326', 'EPSG:4326 (WGS84)']]</pre>

The possible special properties are:

- title_epsg: the caption for the field to select the EPSG code of the coordinates
- title_longitude: the title of the longitude field
- title_latitude: the title of the latitude field
- **coordinatesFieldsOrder**: a list of strings, describing the order in which the three input elements occur
- epsgCodes: a list of tuples, each describing an EPSG code to select and its corresponding label in the form

File upload (type file)

The file upload can be used to link files to a database column in the form. To do this, the uploaded files are stored in Mapbender and the path is noted in the column.

The storage path and the name of the stored files can not yet be changed. The file upload always saves to the same directory and is built up from the parameters:

- tablename
- columnname
- filename

The filesystem path is:

• <mapbender>/web/uploads/featureTypes/[tablename]/[columnname]/[filename].png

The linked URL stored in the database column is:

• http://localhost/mapbender/uploads/featureTypes/[tablename]/[columnname]/[filename].png



Notes: At this time, a "thumbnail" directory is created, which includes a smaller version of an image file. In future development this will be changed.

A possibility to show the uploaded images is the image-element.

Images (type image)



The image-element can be used to view a picture in the form. You can display images by specifying a URL

in a database field or URL using the src parameter.

Images, which are marked by the element file in a table column, can thus also directly be integrated and displayed.

The image can be specified by specifying the two parameters src and name.

- src: Url-path or file path (can be a relative path)
- name: Url-path or file path from the table column (can't be a relative path)
- definition of name and src together: The content of the database column from name is taken. If the column is empty, the src is used.



Caution: If only name and not name and src are specified, the wrong image appears from the previous data entry, if the column is empty.

Dynamic paths (eg "bundles/mapbendercore/image/[nr].png" or 'bundles/mapbendercore/image/' + data.image_reference) can not be specified.

One way to work around this is to create a trigger that will merge the path and contents of a table field into the database column.

Definition of the available toolsets (Toolset Type)

Toolset types:

- drawPoint Draw point
- drawLine Draw a line
- drawPolygon Draw polygon
- drawRectangle Draw rectangle
- drawCircle Draw circle
- drawEllipse Draw ellipse
- drawDonut Draw a Donut (enclave)
- modifyFeature Move vertices of a geometry
- moveFeature Move geometry
- **selectFeature** Geometry de-/select (experimental). There is no interaction with the table yet and the available workflows are limited to the Delete operation.

- **removeSelected** delete selected geometry (experimental). Deletes all objects selected in the map.
- **removeAll** Caution: remove all geometries from the table

```
YAML-Definition of toolset types
```

```
polygon:
  [...]
  toolset:
        - type: drawPolygon
        - type: drawRectangle
        - type: drawDonut
        - type: removeSelected
```

Search in the tables (inline Search)

You can use the inline search to search for an element in the table. The activated element displays a search bar above the table. It shows all the search results for records of the table.

```
poi:
...
inlineSearch: true  # true: allows the search in the table (default: true).
...
```

Context Menu

Using the context menu, an object on the map can be considered in more detail. After the activation you can open a context menu via the right mouse click on an object or cluster.



Items of the Context Menu:

- Zoom to: Zoom to the map extent of the object
- Edit features: Edit the features of the object. Opens the Digitizer dialog.
- **Remove:** Remove the selected object.

If the corresponding *basic definition* (allowEdit, allowDelete) not defined, then they are also not available in the Context Menu. In the above example the delete function is not available for the polygons.

poi:					
	 useContextMenu: true				

Clustering (experimental)

By clustering the objects can be combined on the map. Depending on the defined distance and zoom level different numbers of objects can be clustered.

Due to the complexity of the Clustering, future versions may have changes in functionality and syntax, so we define that still as experimental. Dependencies are to the display of features in the current extent/all areas and the different geometry types.



Definition of the cluster element:

- scale: Zoom level.
- **distance:** distance between features in m to activate the clustering.
- **disable:** zoom level to disable the clustering.

```
poi:
    . . .
    clustering:
            scale: 10000
                                 # Zoom level
                                 # distance between features to cluster
            distance: 60
            scale: 2500
            distance: 40
            scale: 1000
            distance: 20
            scale: 500
            distance: 1
            disable: true
                                 # disable clustering at defined zoomlevel
    . . .
```

Map-Refresh after save

After saving an object, the refresh can be activated using the *refreshLayersAfterFeatureSave* option. This parameter is used to reload the defined layer instances in the map-element. This makes changes regarded to WMS services directly visible in the map. This event is thrown only if the "Save" button of the attribute dialog is pressed.

If the YAML application is used in the /application folder, it can be specified by a unique name or by the instance-ID. If the applications are edited using the graphical user interface in the *Backend* with the digitizer-element, it can be specified by the instance-ID.

YAML -	main		
Id	Titel	Тур	+ 🖉 ×
5'17	Mapbender Users (mapbender_users)	WMS	• / ×
poi: [all ref → after - - -] owEdit: true reshLayersAfterFeatureSave: # If no entry is made in this area no saving 17 18 osm # specify by unique name only with applications in app]	map refresh is lications/	carried out <mark>l</mark>

Notes: Map-Refresh after save is available from Digitizer version 1.2. Check up-to-date information about digitizer versions: https://github.com/mapbender/mapbender-digitizer

Duplicate features

Already captured objects can be duplicated. This is done via a duplicate-button within the popup of the current selected already existing feature, via the context menu and the hit table. In order for the new object to be recognized better in the map, a color highlighting can be defined here.

The Duplicate button can be activated depending on a specific attribute value. This means that only when the corresponding attribute has a specific value (date> 0) the duplicate function works.

- data: Define default values for attributes.
- **rules**: Rule based duplicating (only if the filter/rule is active the object can be duplicated).
- **style**: Styling of the duplicated feature (more at Design and Styles)
- on: Events while duplicating process

```
poi:
    [...]
    copy: # If no specification is made in this area you can't duplicate objects
    enable: true
    data:
        date: 2017
    rules:
            feature.attributes.id > 10
    style:
```

(continues on next page)

```
label: "Dupliziertes Objekt"
fillColor: "#ff0000"
fillOpacity: 1
strokeWidth: 4
strokeColor: "#660033"
on:
success: widget._openFeatureEditDialog(feature)
error: console.error(feature)
```

Events

Different events exist that can be associated to a feature to manipulate attributes before or after an action.

- **onBeforeSave**: Event before the storage of a new/modified information
- **onAfterSave**: Event after the storage of a new/modified information
- onBeforeUpdate: Event before the update of a modified information
- onAfterUpdate: Event after the update of a modified information
- onBeforeSearch: Event before the search in the SearchField of the Digitizer
- onAfterSearch: Event after the search in the SearchField of the Digitizer
- onBeforeRemove: Event before deleting data
- onAfterRemove: Event after deleting data

In difference to the save-events, the update-events work only on an update of the data, not on creation.

Note: The events are still in development and should be used with caution. The correct matching of the events and their dependencies are not yet finished and may be changed in future versions.

The following sections show some examples. If you want to set several parameters in an event, these can be listed in sequence, separated by a semicolon, e.g.

```
events:
    onBeforeSave: $feature->setAttribute('interests', 'maps'); $feature->setAttribute('name', 'test');
```

Storage of predefined attibute data in an additional attribute-columns:

The following example shows how data can be written to an additional attribute column. This is done with the column "interests" and the fixed value "maps". When saving, the fixed value is stored in the table and you can use it via a filter for the selected display.

```
events:
    onBeforeSave: $feature->setAttribute('interests', 'maps');
```

Storage of group roles in an additional attribute-columns:

The following example shows how mapbender user data can be written to an additional attribute column. Here, this is done with the column "group" and the storage with the group roles of the user (userRoles).

events: onBeforeSave: \$feature->setAttribute('group', implode(',', \$userRoles));

Storage of attibute data in an additional attribute-columns:

This example shows how data can be stored in an additional attribute-column after saving. In this case it is done with two geometry-columns "geom" and "geom2". When saving, the data of "geom" should be saved in the field "geom2".

Depending on the use case, the onBeforeInsert or the onBeforeUpdate event can be used.

At the time of the saving-process the new geometry doesn't yet persist in the database. Therefore it cannot be accessed as a feature but only via the corresponding "item", an internal Digitizer structure. This "item" is based on the formular and the defined attribute fields.

```
events:
    onBeforeInsert: $item['geom2'] = $item['geom'];
    onBeforeUpdate: $item['geom2'] = $item['geom'];
```

In this event the value of "geom2" is overwritten with the value of "geom".

Storage of different geometry-types:

The above scenario can be extended to a slightly constructed example in which simultaneously different geometry types shall be saved. With the help of PostGIS, lines are interpolated to points. The Digitizer can use an event to fire the according SQL statement.

```
events:
onBeforeInsert: |
$sql = "SELECT
ST_Line_Interpolate_Point('".$item['geomline']."'::geometry, 1) as geom";
$stmnt = $this->getConnection()->prepare($sql);
$stmnt->execute();
$result = $stmnt->fetchAll();
$item['geompoi'] = $result[0]['geom'];
```

The onBeforeInsert event is used here. The pipe symbol "|" after the event signals a following multiline statement. This blog contains PHP code, which calls SQL-statement. The SQL-statement calls the ST_Line_Interpolate_Point function of PostGIS and commits the digitized line. Because this line is not yet persisted in the database, you have to access it with the "item" (geomline). The next lines build up the SQL-statement and delivers it to the SQL-connection defined in the featuretype. The last line writes the resulting point (geompoi) into the point-geometry-field.

Buttons

Further buttons can be defined for the popup forms. The events (by clicking on the buttons) can be freely defined with JavaScript. Thus, for example, mailto data can be generated for the integration of a mail.

```
poi:
...
popup:
   title: polygon test suite
   width: 500p
   # resizible: true
   buttons:
        - text: message to editor
        click: |
        var body = encodeURI("Sehr geehrter Herr/Frau xx,"+"\nLink:"+location.href);
        location.href = "mailto:firstname.lastname@mail.com?subject=New edit in webgis&
   -body=Mail to editor for further edits.";
```

(continues on next page)

```
- text: message to controller
click: |
location.href = "mailto:firstname.lastname@mail.com&subject=webgis&body=really?";
```

Design and Styles

By specifying a style the way the objects are displayed on the map can be defined.

- **default**: defines the normal display of the objects on the map
- select: defines the appearance of the objects while mouseover
- selected: defines the appearance of the objects after click event

```
poi:
    . . .
    styles:
        default:
            graphic: true
            strokeWidth: 5
            strokeColor: "transparent"
            fillColor: '#c0c0c0'
            fillOpacity: 1
            fillWidth: 2
            # label: ${name} ${type}
            # labelOutlineColor: '#eeeeee'
            pointRadius: 10
        select:
            strokeWidth: 1
            strokeColor: "#0e6a9e"
            fillOpacity: 0.7
            fillColor: "#0e6a9e"
            label: ${name} ${type}
            pointRadius: 10
        selected:
            strokeWidth: 4
            strokeColor: "#648296"
            fillOpacity: 1
            fillColor: "#eeeeee"
            label: ${name} ${type}
            pointRadius: 10
    . . .
```

- **strokeColor:** Color of the border line [color value/transparent]
- strokeWidth: Width of the border line [numeric]
- **strokeOpacity:** Transparency of the border line [0-1]
- fillColor: Color of the filling [color value/transparent]
- fillwidth: Width of the filling [numeric]
- fillOpacity: Transparency of the filling [0-1]
- pointRadius: Radius around the center [numeric]
- label: Labeling the object with fixed values and / or DB fields, e.g. "ID \${nummer}"

• labelOutlineColor: Color of the border from the label [color value/transparent]

YAML-Definition for the element Digitizer in mapbender.yaml

This template can be used to insert the element into a YAML application.

```
sidepane:
    digitizer:
        class: Mapbender\DigitizerBundle\Element\Digitizer
        title: Digitalisation
        target: map
        schemes:
        ...
```

More information about the functionality of the digitizer can be found here:

Functionalities

Digitizer allows the editing of FeatureTypes. These are based on points, lines or polygon geometries and their attribute data. The attribute data is displayed in the configurable form of the Digitizer element. Geometries can be edited directly via the map. Digitizer offers complex editing functionalities:

- Draw points, lines, polygons, rectangles, ellipses or circles
- Move objects
- Add vertices (to lines or polygons)
- Generate areas with enclaves



The following sections explain the different functionalities of Digitizer in accordance with its default configuration.

Draw geometries

When drawing geometries, one can choose between the geometry types "point", "line" or "polygon" via a dropdown menu.

Points

A click on the button "draw point" activates/deactivates the option to draw points.

-
•

Lines

A click on the button "draw line" activates/deactivates the option to draw lines.

150
H

Polygons

Polygons, rectangles, enclaves, ellipses and circles can be drawn after activation of the corresponding button.



After activation, an object can be created through one or more clicks on the map. Afterwards, a pop-up window will appear, which requests attribute data in correspondence to its configured YAML-configuration.

Edit, save or delete geometries

Objects are saved in the defined database table. The objects are displayed on the map and additionally as a table in the sidepane. This simplifies the administration of data. You can define which columns to list via the configuration. In this configuration the number (ID is automatically created after saving) and name of each object are displayed. It is possible to sort the columns or to search in the columns.

The list can also only display geometries of the current extent **1**. It is possible to hide **2** or show **3** all objects via click on the corresponding buttons. Modifications can be saved for all objects **4**. A change would, for instance, be the movement **5** of an object. After the button has been activated, geometries can be moved on the map with the mouse.

Furthermore, individual objects can be hidden **6** and changes saved **8**. You can change the attribute data **7**. Every object can be deleted **9**.

 Ø> 2 3 iltori 	 e^ℓ 4 5 	
inter:		
追 Nr.	♦ Name	
	Test A	💿 🖉 🖹 🗙
41		

Previously described functions are identical for all geometries. Additionally, intermediate points can be added to lines and the corners of areas modified. This option is activated via click on the Button *"Edit"*. In order to modify an object, it has to be selected beforehand.

Digitizer		Digitizer
line digitizing	•	polygon digitizing
Select by current extent only		Select by current extent only
Ø @ B / 75 4		
Filter:		Filter:
Ĵ≟ Nr. ♦ Name		<mark>↓≟</mark> Nr. ♦ Name
28 Test A	👁 🖻 🖹 🗙	80 Test A 🖉 🖻 🕽
Showing 1 to 1 from 1		Showing 1 to 1 from 1

3.2.2 Data Manager

The element Data Manager is similar to the *Digitizer*. However, Data Manager only works with nonspatial data, i. e. you can not create geometries. Data Manager can be used to maintain reference tables, for example a table with contact information.

Configuration

Data Manager needs access to a database where the editable tables are. You have to define a new database configuration to be able to connect with. Read more about this under YAML Configuration (Configuration and Application files).

Configuration example

The definition of the Data Manager is done in YAML syntax in the textarea configuration at schemes. Here you define the database connection, the editable tables, the attribute form.

Hint: If errors occur in the database, fields or form, various error messages will appear. Here, the productive environment will only give a general error message. If you want to see the exact error, you should call the page as development environment. Find more under en/quickstart:Start Mapbender in a productive environment.

Data Manager is a good solution to store simple contact information in Mapbender:

ontact	s	
C +		
Filter:		
last name	^{†↓} first name ^{↑,}	L
Eddie	Eimer	Ĩ
Gustav	Gans	
Mandi	Meier	ľ
Max	Mustermann	ľ
Rüssel	Rudi	ľ
Tester	Thilo	21
	Showing 1 to 6 from 6	

+

In the example, an input template is opened after clicking

Contacts				×
Example for element Data Manager				
last name		first name		
Please enter your last name.				
street house nur	nber	postcode	location	
date_favorite		color favorite		
mm / dd / yyyy	Ö	#ff0000		
phone number 🖲 🔒		email 🛈 🔒		
notes				
Guter Tester				
				1
publish contact				
Information				
user: undefined Datum:undefined				
Choose one				
Option 1				
Option 2 Option 3				
Select at least one (multiple choice)				
Option 1				
Option 2 (disabled)				
Option 3				
Option 4				
			Save	Cancel

SQL for the contact table

The following SQL commands must be executed in your database to create the contact table for the example.

```
CREATE TABLE public.contacts (
    gid serial PRIMARY KEY,
    firstname varchar,
    lastname varchar,
    street varchar,
    housenumber varchar,
    postcode integer,
    location varchar,
    phone varchar,
    email varchar,
    notes varchar,
    public boolean,
    date_of_creation date DEFAULT date(now()),
    user_of_last_edit varchar,
    date_favorite date,
    color_favorite varchar
);
```

Element configuration

Afterwards, the element can be embedded into the sidepane.

Edit element						
Title	Data manager					
Schem	25					
1 0	contacts:					
2	dataStore:					
З	connection: geodata_db					
4	table: contacts					
5	uniqueId: gid					
6	events:					
7	onBeforeSave: '\$feature->setAttribute(''user_of_last_edit'', \$user); '					
8	allowEdit: true					
9	allowCreate: true					
10	allowDelete: true					
11	allowRefresh: false					
12	popup:					
13	title: contacts					
14	Width: 550px					
15	Tormitems:					
10	-					
1/	children.					
10						
19						
20	type: labet tile: "Yyample for element Data Manager"					
22	titte. Example for element bata nanager					
23	type: fieldSet					
24	children:					
25	-					
26	type: input					
27	title: last name					
28	attr:					
29	placeholder: 'Please enter your last name.'					
30	name: lastname					
31	CSS:					
32	width: 50%					
33						
	Save Cancel					

YAML-Definition

You can find the necessary YAML code of the configuration example below:

```
contacts:
 dataStore:
   connection: geodata_db
   table: contacts
   uniqueId: gid
   events:
      onBeforeSave: '$feature->setAttribute(''user_of_last_edit'', $user ); '
  allowEdit: true
  allowCreate: true
  allowDelete: true
  allowRefresh: false
 popup:
   title: contacts
   width: 550px
  formItems:
      type: form
      children:
```

(continues on next page)
```
type: label
title: 'Example for element Data Manager'
type: fieldSet
children:
    type: input
    title: last name
    attr:
        placeholder: 'Please enter your last name.'
    name: lastname
    css:
      width: 50%
    type: input
    title: 'first name'
    name: firstname
    css:
      width: 50%
type: breakLine
type: fieldSet
children:
    type: input
    title: street
    name: street
    css:
      width: 30%
    type: input
    title: 'house number'
    name: housenumber
    css:
      width: 20%
    type: input
    title: postcode
    name: postcode
    css:
      width: 20%
    type: input
    title: location
    name: location
    css:
      width: 30%
type: fieldSet
children:
    type: date
    title: date_favorite
```

(continues on next page)

```
name: date_favorite
      css:
        width: 50%
      type: colorPicker
      title: color favorite
      name: color_favorite
      attr:
        placeholder: '#ff0000'
      css:
        width: 50%
#-
# type: breakLine
 type: fieldSet
 children:
      type: input
      title: phone number
      name: phone
      mandatory: true
      mandatoryText: 'Please add your phone number.'
      infoText: 'Help: Please add your phone number.'
      copyClipboard: true
      css:
        width: 50%
      type: input
      title: email
      infoText: 'Help: Please add your e-mail.'
      copyClipboard: true
      placeholder: 'Please enter your e-mail.'
      name: email
      css:
        width: 50%
  type: breakLine
 type: textArea
  title: notes
  placeholder: 'You can leave notes here.'
 name: notes
 value: 'Guter Tester'
 type: checkbox
 name: public
 value: true
 title: 'publish contact'
 type: text
 title: 'Information'
 text: "'user: ' + data.user_of_last_edit + ' Datum:' + data.date_of_creation\n"
- type: radioGroup
 title: Choose one
 name: choice_column_1
  options:
```

(continues on next page)

```
- label: Option 1
            value: v1
          - label: Option 2
            value: v2
          - label: Option 3
            value: v3
                   # Pre-select second option by default for new items
        value: v2
      - type: select
        title: Select at least one (multiple choice)
        attr:
          required: required
          multiple: multiple
        name: choice column 2
        options:
          - label: Option 1
            value: v1
          - label: Option 2 (disabled)
            value: v2
            attr:
              disabled: disabled
          - label: Option 3
            value: v3
          - label: Option 4
            value: v4
        value: v1,v3 # use comma-separated values for default multi-select value
table:
  autoWidth: false
  columns:
      data: lastname
      title: last name
      data: firstname
      title: first name
 info: true
 lenghtChange: false
 ordering: true
 pageLength: 10
 paging: true
 processing: true
  searching: true
```

3.2.3 Sketches

The Sketches element allows creating, editing and deleting temporary objects. Sketches are not saved within a database and will be lost after the browser window is refreshed or closed. Sketch geometries will be exported into *Image Export* and *PrintClient*.

The following geometry types can be sketched:

- Point
- Line
- Polygon
- Rectangle

- Circle
- Text

Configuration

Add element Map area - Sketches						
 Open automatically Deactivate on close 						
Title	Sketches					
Geometry types*	Point Line Polygon Rectangle					
Colors	#ff3333,#3333ff,#44ee44					
✓ Allow custom of the second seco	olor					
	Back Add Cancel					

- Open automatically: Opens the Sketch element on application start (default: off).
- **Deactivate on close:** Sketches are deactivated after closure of the element.
- Title: Title of the element. This is referenced by the button which opens the element.
- **Geometrytypes:** Lists all geometrytypes (mandatory field).

- **Colors:** Creates buttons for custom colors in the Sketch tool. Color values must be comma separated. Needs at least one input color (mandatory field).
- Allow custom color: Creates a custom color picker in the Sketch tool. Disable to show only the defined CSS colors.

Draw geometries

- **Point drawing:** is activated with a click on the "Point" button. Points are set with a simple click on the map and will appear in the Sketches table.
- Line drawing: is activated with a click on the "Line" button. Line segments are set via a single click on the map. To finish drawing, double click.
- **Polygon drawing:** is activated with a click on the "Polygon" button. Vertices are set via a single click. To finish drawing, double click anywhere in the map or single click on the last drawn vertex.
- **Rectangle drawing:** is activated with a click on the "Rectangle" button. Rectangles are created by two single clicks.
- **Circle drawing:** is activated with a click on the "Circle" button. For a circle, two single clicks are sufficient: One for the position of the circle center and one for the circumference. After the circle was created you can edit it and set a radius.
- **Text labels:** are activated with a click on the "Text" button. A label has to be defined in the label field before a text is set.

See the image below for sketch examples:



Delete, Edit and Zoom

Drawn sketches can be individually deleted [1] or edited [2]. There is also the possibility to zoom to a particular geometry [3].

Color picker

It's possible to pick colors after setting up the configuration parameters (see above). If done correctly, buttons offering the colors will appear. Clicking on one of the color buttons determines the color for the next feature drawn, or, if currently editing a feature (click on "Edit geometry" icon in table listing), immediately updates that feature to that color. This will work with the geometry that isn't saved to the table yet, too. The color picker that can be activated with **Allow custom color** in the configuration menu allows a free choice of color at the application level. If the element is configured with only a single color and the frontend color picker is disabled, the color region will not be shown and the default color will be used for all geometries instead.

Stop drawing

To interrupt a drawing, click the stop button: Note that this deletes your current draft.



YAML-Definition

This template can be used to insert the element into a YAML application.

```
tooltip: 'Sketch'
                                # text of the tooltip Tooltips
                                # ID of the element
target: ~
                                # (default: false)
auto_activate: false
                                # Drawn sketches will be deactivated if the element is closed
deactivate_on_close: true
→(default: true)
geometrytypes: point,line,polygon,rectangle,circle,text # list of available geometry types
                                # Mentioned Hex color codes will be implemented into the tool
colors:
 - '#ff3333'
                                # Default color red
 - '#3333ff'
                                # Default color blue
 - '#44ee44'
                                # Default color green
                                # Implements a custom color picker for user color selection (default:
allow_custom_color: true
→true)
```

3.3 Export / Print

3.3.1 Image Export

Image Export allows you to export your current map view. You can choose .png or .jpg format.



Configuration

Add element Map area - Image export				
Title	Image export			
		Back Add Cancel		

• **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. The title will be displayed besides the button if "Show label" is activated.

YAML-Definition

This template can be used to insert the element into a YAML application.

```
class: Mapbender\PrintBundle\Element\ImageExport
target: map  # Id of Map element to query (e.g. map)
```

You need a button to show this element. See *Button* for inherited configuration options.

3.3.2 PrintClient

The PrintClient enables printing of a predefined map area. This documentation provides an overview of its setup and configuration, outlines the generation of individual print templates, and details the print process along with its configuration options.

General

It is possible to define different properties of the PDF you would like to print with the client:

- Template
- Quality
- Scale
- Rotation
- Title
- Print legend checkbox

Print	×
Template*	
A4 Portrait	~
Quality*	
Draft (72dpi)	~
Scale*	
1:25000	~
Rotation*	
0	
Title*	
Print legend	Print Close

The PrintClient element can be implemented both as a dialog (via a button) and as element as part of the sidepane. If it is part of the sidepane, you have to activate the print frame first to start the print. The print frame can be moved around freely in the map canvas, it defines the area of the PDF output. When finished, you have to deactivate the print frame to use the map as usual again (when used as a dialog this happens automatically by opening and closing the dialog window).



Configuration

The Printclient is configured in the backend. It relies on print templates (A0 to A4). These LibreOffice Draw files can be individually modified regarding the location of date, scale, north arrow, overview map as well as dynamic images/texts in the PDF.

Add element						
Map area - Print						
Title	Print					
Scales (comma- separated)	25 500,1000,5000,10000,25000 Ima- Irrated)					
🖌 Rotatable						
🗹 Print legend						
Legend checkb	pox active					
File prefix	mapbender					
Quality levels						
Dpi 72		Label	Draft (72dpi)			
Dpi 288		Label	Document (288dpi)			
Templates* +						
Template	a4portrait		Û			
Label	A4 Portrait					
Template	a4landscape		Î			
	· •		Back Add Cancel			

- **Title**: Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. The title will be displayed next to the button if "Show label" is activated.
- Scales (csv): define scales to choose from selectbox, or if empty a free scale can be defined in a text field.

- Rotatable: defines if the print extent is rotatable, default is true
- Print legend: adds a checkbox which allows your print to have a legend
- Legend checkbox active: if true, the legend checkbox is checked by default
- **File prefix**: defines a file prefix for the PDF that is generated when creating a PDF (file_prefix_date.pdf will be created)
- **Quality levels**: defines quality levels in DPI values.

Templates

- **Template**: Template name. Add template file name without file extensions (Mapbender is looking for two files, e.g. a4portrait.odg & a4portrait.pdf), Template files are located at con-fig/MapbenderPrintBundle. Deleting or adding templates is possible with the "+"- or "x" buttons.
- Label: Template label description for the selectbox in the frontend.

Optional fields

With the configuration of the following values it is possible to enable optional fields in the print dialog. An example (title, two comment fields, name) is offered in the YAML definition.

- title: name of the optional field, default value is null (no optional fields are defined).
- **label**: Label of the optional field.
- **options**: Type of the optional field. Has to be true or false.
- Display required fields first: If this checkbox is active, your defined required fields appear utmost.
- **Replace pattern**: You can modify the map request for printing. You can add additional parameters like map_resolution (for MapServer).

Here's an example for the *Backend* configuration (or look below in the YAML definition for an enhanced and commented example).

Optional fields	title: label: Title options: required: true
Display require	ed fields first
Replace pattern	- default: 288: '↦_resolution=288' -
	pattern: mapbender_user replacement: 288: mapbender_user_2
	Save Cancel

YAML-Definition

This template can be used to insert the element into a YAML application.

```
target: map
                               # Id of Map element to query
type: dialog
                               # element or dialog, default is dialog
templates:
    - { template: a4portrait, label: A4 Portrait} # template name, template file name without file
→extension (Mapbender is looking for file a4portrait.odg an a4portrait.pdf), Template files are
→located at config/MapbenderPrintBundle
    - { template: a4landscape, label: A4 Landscape}
                                                           # template label in the dialog
scales: [5000, 10000, 25000] # define scales to choose from select-box or if empty free scale can be
\rightarrow defined in a text-field
quality_levels:
                                                    # define quality levels in dpi
    - { dpi: 72 , label: Draft (72dpi)}
                                                    # 72 - dpi value, Draft - label
    - { dpi: 288, label: Document (288dpi)}
                                                   # 288 - dpi value, Document - label
rotatable: true
                               # true/false use true for rotation (default: true)
legend: true
                                # true/false to print a legend (default: false)
legend_default_behaviour: false # true/false, if true the legend checkbox is checked by default
file_prefix: mapbender
                              # define the file prefix for the PDF that is generated (file_prefix_date.
\rightarrow pdf will be created)
optional_fields:
                                # define optional fields (example title-field)
                                # name of the optional fields, default is null (no optional fields are]
   title:
\rightarrow defined)
        label: Title
                                # label of the optional field
        type: text
                                # type of the optional field
        options:
                                #
            required: false
                                # true/false
```

(continues on next page)

```
comment1:
        label: Comment 1
       options: { required: false }
    comment2:
        label: Comment 2
        options: { required: false }
   editor:
       label: Editor
        options: { required: true }
                                 # You can modify the map-request for printing
replace_pattern:
                                 # you can add additional parameters like map_resolution (for MapServer)
            default: { 288: '&map_resolution=288' }
            pattern: 'stadtplan.xml' # or you can request a different service which is optimized
\hookrightarrow for printing
            replacement: { 288: 'stadtplan_4.xml' }
```

Directories

The northarrow

- The "north arrow" image is located at config/MapbenderPrintBundle/images/.
- The "north arrow" image can be replaced to use a different image instead.

The print templates

• The print templates can be found under config/MapbenderPrintBundle/templates/.

The print pdf output

- Mapbender displays the generated PDF directly in your browser and provides it for download.
- If the queued print is used, the files will be saved under the Mapbender directory **public/prints/**.

Create your individual templates

To create an individual print template, already existing print templates (.odg-file) can be copied, or a new LibreOffice Draw file can be used. The template can include fixed objects like a logo, copyright or print information. In addition, a layer for dynamic elements like map, overview, north arrow, scale, date and optional fields can be created. The dynamic layer is an additional non-printable layer in the LibreOffice Draw file. The layer can be added with **Menu: -> Add -> Layer -> define name for the layer and choose checkbox option "not printable"**. An element is assigned to a layer via drag and drop.



The following objects are available by default in Mapbender:

- map
- overview map
- scale
- scalebar
- date
- northarrow
- extent_ur_y, extent_ur_x, extent_ll_x, extent_ll_y (coordinates of the print extent)
- dynamic_image (connected to group role)
- dynamic_text (connected to group role)

Optional fields in the element definition (e.g. title, comment, editor) can be defined and added to the Open Office Draw file. They need to be inserted into the non-printable area of the file, or else they will appear in the generated template PDF.

When creating dynamic texts, each property must have the appropriate name, for example the field **com-ment1** must have the name **comment1** in the Open Office Draw file. For naming fields, it is not enough to apply the name to the content of the text field. Instead, the field needs to be selected and its object name edited. Select text field [] **Menu Edit** [] **name...** to change the name accordingly.

80 Datei	print_template_odg.odg - LibreOffice Draw						
	r 🛅 r 🔜 r 💽 🥂 🛱	¥∎ ® · <u>≜</u> +	Drehen Spiegeln Umwandeln	۶ ۲		27 🤌 🗐 🔀	· ·
- - - -			Anordnung Ausrichtung Verteilung	<i>}</i>			
/			Name				
			Gruppieren Gruppierung aufheben Gruppe betreten	Umschalt+Strg+G Umschalt+Strg+Alt+G F3		•	-
→ • ∡ • গ			Gruppe verlassen Kombinieren Teilen	Strg+F3 Umschalt+Strg+C Umschalt+Strg+Alt+C			
در ب م			Formen Verbinden	•			
			Aubrechell	n	orth	arrow	•
, 		- - -			UIU		
•							

Export the template to .pdf under the same name as the .odg file. Use the name without its extension in the print yml-definition.

The print script will read the information (position, size, font size, alignment) from the .odg-file and combines those with the fixed objects in the PDF template and the map image in Mapbender to generate your PDF.

Printing elements in front of the map element

In order for the map element to be as large as possible and to avoid white or empty areas, elements can be placed in front of the map image to prevent that space is lost through white areas. This is particularly useful in the case of large printing formats which have a comparatively wide border.

To use this function, the templates have to be adapted and transparent PDF templates have to be created.

Adapt templates:

- Reorder elements in front of white background
 - Arrange elements into the foreground (right-click Arrange [] To the front)
 - Arrange map element into the background (right-click Arrange [] To the back)
- Select all
 - Press CTRL + A
- Print selection as PDF
 - Export as PDF
 - Selection instead of All

Legend on the first page

The legend can be integrated next to the map on the first page. This field is not included in the print template by default. To insert the legend the ODG print template file needs to be modified. A new dynamic field with the name "legend" on the non printable layer needs to be inserted. **Menu: Modify -> Name...** to change the name of the field to "legend". As final step, the ODG-file has to be exported as PDF-file as described above and saved in the same directory. The result could look like this:



Logo on the legend page

If the legend shall be created on an additional page, the logo can be placed on this page too. This can be achieved with the dynamic element "legendpage_image". A new field on the non-printable layer has to be created and the name changed to "legendpage_image" (**Menu: Modify -> Name...**). The desired logo or image has to be saved in the directory **config/MapbenderPrintBundle/images/** and its name needs to be changed to "legendpage_image".



Coloured texts

The text in the print template can be changed in many ways. Besides the size of the font, one can also change the colour of the text. To do so, a text field via **Menu: Insert -> Text Box** needs to be inserted. To change the colour of the text, select the text in the text field (here: "title"). The colour can be changed in the tab **Properties -> Character**:



Or right-click the selected text [] dialogue window Character [] Font Effects [] Font color.

chriftfarbe:		Überstreichung:		Farbe:	
Schwarz	•	(Ohne)	-	Automatisch	Ŧ
ffekte:		Durchstreichung:	,		
(Ohne)	-	(Ohne)	-		
Relief:		Unterstreichung:	,	Farbe:	
(Ohne) 👻		(Ohne) 👻		Automatisch	
🗌 Kontur	-	U Wortweise			
Schatten					
		4.41 -			

The change of the colour of the dynamic field "title" to blue can look like this:



The change of the font size works in an analogous manner.

Dynamic images and dynamic texts

Dependent on a group, prints can be created with different logos and texts (e.g. the name of the commune and the individual logo). There are two objects which can handle this: "dynamic_image" and "dynamic_text". If these objects exist in the print layout [Mapbender and the user are members of a group], Mapbender will then search for an image with the name of the group (groupname.png). The picture will be displayed in the print in the object ["dynamic_image"]. The height of the object will be used to scale the image[,] the width will be calculated relative to the height. In the object ["dynamic_text"] the group description will be printed.

Depending on the group, the print can contain different images or descriptions (e.g. logo and name of the commune). This can be achieved through the dynamic elements "dynamic_image" and "dynamic_text". One can insert both elements in the ODG-print template on the non-printable layer and change their names (**Menu: Modify -> Name...**).

Note: Only one dynamic image and dynamic text of a group description will be printed. In other words: Mapbender always takes the first group into account. If a user is member of both groups "intern" and "Group 1", then "intern.png" is taken as dynamic image and the group description of "intern" will be adopted into the dynamic text field.

The print with a group named "Group 1" could look like this:



To use this feature, it is required that groups exist. How to create groups and users is described in the Mapbender documentation in the *Mapbender Quickstart*.

The description of the group will be displayed in the field "dynamic_text" (e.g. copyright message). The element "dynamic_text" looks for a group description that is given in the first assigned group of the print. You can implement the dynamic text independently from the dynamic image.

It is possible to print a user name. In order to do this, one has to insert **user_name** into their print template. The logged-in user's name is then printed at the defined location. If no user is logged in, nothing is printed.

දිදි 5620760	root		lee
w Aoo	Test	Scale: 1:10000	Date: 27.11.2020
s		-	

The printing process

Printing feature information for a selected element

A feature can be selected via digitizer or Feature Info.

The concept is to pass the feature_type-name and the selected object ID to the print. Mapbender will then get all the feature data for the selected object and will look for fields in the print template. If a print template field is defined, the data will be printed to this field.

In the next steps it is described how this functionality can be configured. The documentation relies on the POI table that is used in the digitizer example.

You find the configuration and an example print-template in the Workshop/DemoBundle at https://github.com/mapbender/mapbender-workshop

There are some steps you have to follow:

- 1. Create a print template that refers to the feature columns
- 2. Define a featureType and refer to your new print template in your doctrine.yaml
- 3. Call feature print from FeatureInfo
- 4. Or call feature print from digitizer

1. Create a print template that refers to the feature columns

Define text fields in the print template for every information you would like to print for the selected object. The text field name has always the prefix *feature*., followed with the name of the attribute (column) to export.

feature.name for column name of table poi

2. Define a featureType and refer to your new print template in your doctrine.yaml

parameters:	
featureTypes:	
feature_demo:	
<pre>connection: search_db</pre>	# Name of the database-connection from the doctrine.yaml
<pre>table: public.poi</pre>	# Table-name in which the FeatureTypes are stored
uniqueId: a_gid	# Column-name with the unique identifier
<pre>geomType: point</pre>	# Geometry-type
geomField: geom	# Column-name in which the geometry is stored
srid : 4326	# source EPSG-code of data
print:	# print template to offer for feature data print
templates:	
 template: a4_ports 	-ait_official_feature_data_demo
label: Demo with t	feature information print (portrait)
 template: a4_lands 	scape_official_feature_data_demo
label: Demo with	Feature information print (landscape)

3. Call feature print from FeatureInfo

Note: FeatureInfo is the information output from a OGC WMS service. It offers information for features at a click position.

When you configure a WMS, you can generate a link with the following reference that will trigger the print with feature information.

The following code is an example for a MapServer information template.

```
<tc><cript src="http://code.jquery.com/jquery-latest.js"></script>

<class="th_quer">Print
```

The FeatureInfo will open a dialog with a link *print feature information*. When you click on the link, the print dialog opens and offers the print templates that are defined for the feature type.

You can choose the desired region and create a print PDF. The PDF will contain the information for the selected feature.

4. Or call feature print from digitizer

The functionality can also be integrated in the digitizer. It will offer a new button *print* in every feature information dialog.

To activate the functionality, add the following parameter to the digitizer configuration.

printable: true

With click on the print button the print dialog opens and offers the print templates that are defined for the feature type.

Note: The flexibility to move the print frame won't stop you from choosing a region that does not contain the feature that was selected. In this case, the feature information does not match to the features that are displayed.

Queued Print

The queued print is an experimental print feature for Mapbender which comes with an advanced background print system. Right now, it's still in experimental state due to several potential cache memory regeneration problems on more complex server structures. The queued print is implemented since Mapbender 3.0.8, but deactivated by default. If you choose to activate it, you can use the feature via command line (either manually or as a cronjob). Queued print helps improving resource-intense print jobs, because the queue can manage the print jobs more easily in the background (compared to direct print). In the meantime, you're free to work with Mapbender in other ways.

Queued print: Configuration

To activate the queued print, open the parameters.yaml file of your Mapbender installation and insert the following parameter:

mapbender.print.queueable: true

To deactivate the queued print, either set the parameter to 'false' or delete the whole parameter. As soon as the queued print section is set to true, you can configure a queued print in the Mapbender backend. Open your PrintClient element and adjust the new options "Mode" and "Job queue". To activate the queue, set "Mode" to 'queued'. 'Direct' will implement the default print surface to your Mapbender application. Moreover, the privacy preferences of your print queue are changeable via the "Job queue" field ('global' or 'private'). After adjusting, save the element and open the application.

Mode	queued	~
Job queue	global	~

Queued print: Bash commands

After the setup, the queued print can be controlled with several bash commands, which are as follows:

mapbender:print:queue:clean
mapbender:print:queue:dumpjob
mapbender:print:queue:gcfiles
mapbender:print:queue:next
mapbender:print:queue:repair
mapbender:print:queue:rerun
mapbender:print:runJob

Note: To run the commands, open a terminal and head to the Mapbender application directory. Find detailed information on the commands under *bin/console commands*.

Queued print: Usage

When using the queued print in the frontend, there are two options: The tab "Job settings" offers the same print settings as the direct print. If the queued print has been set up right, a tab called 'Recent jobs' appears next to the 'Job settings' tab. If this tab is chosen, a chronological list of your print jobs will be shown. A new job will appear in the list after the "Print" button is clicked.

Prin	it client		(8)
Job	settings Recent jobs		
#	created	status	
5	11/13/2019 2:26:08 PM	finished	A ×
4	11/13/2019 2:25:36 PM	finished	A×
3	11/13/2019 2:25:06 PM	finished	A×
2	11/13/2019 2:24:52 PM	finished	A×
1	11/13/2019 2:24:38 PM	finished	A×
		Print	Cancel

To start the printing process, type in the bash command

bin/console mapbender:print:queue:next --max-jobs=0 --max-time=0

to execute a print process in the command line. This process starts all the jobs that are added into the print queue list automatically. Alternatively, you can choose to adjust the parameters and create a fitting cronjob. Terminate the process with 'CTRL + C'. If a print job is finished, it will be listed as "finished" in the status column of the list. Afterwards, the PDF button will open the printable PDF file.

Memory Limits

Queued Print

Print jobs can be resource intensive and may exceed your initially set php.ini memory limit. Therefore it is possible to increase the required memory limit manually. This is an advantage for users who are working with large print templates.

Note: Never reduce the memory limit.

To increase the memory limits for the queued print, adjust *mapbender.print.queue.memory_limit* (string; default is 1G). Caution: This parameter does not allow 'null' as value.

Direct Print

To increase the memory limit of the direct print, adjust *mapbender.print.memory_limit* (string or null; default is null) to your possible memory contigent. If the parameter is set to 'null', Mapbender print will look for your php.ini value. If you set the parameter to a value which is accepted by your php.ini-configuration file, Mapbender print uses this limit instead of the php.ini limit (possible values are e.g. 512M, 2G, 2048M, etc.) Use '-1' for unrestricted memory usage.

Set a WMS Tile Size Limit

If the printing process fails to export a WMS service into the PDF file, the following amendment needs to be made in the parameters.yaml file. This is because, under certain circumstances, the requested pixel size for the WMS is too large, resulting in the service no longer delivering images.

mapbender.imaageexport.renderer.wms.max_getmap_size: 8192

These limitations set the maximum possible WIDTH= and HEIGHT= values for the export request. In the GetCapabilities request of the respective service, the maximum resolution is defined under *MaxWidth* and *MaxHeight*, which means that the getCapabilities request already sets the limit - *8192* is the default value, which may need to be further adjusted. The mentioned parameters can also be defined independently of each other: Use mapbender.imageexport.renderer.wms.max_getmap_size.x for the **WIDTH=** parameter and mapbender.imageexport.renderer.wms.max_getmap_size.y for the **HEIGHT=** parameter.

3.4 Search

3.4.1 Search Router

The Search Router element enables users to locate items within the map by interfacing with a specified database connected via the *Backend*. Both the search form and table output are customizable and facilitate generic SQL search functionality via PostgreSQL tables. This is achieved through the storage of geometries in the database, allowing users to query and display dynamic results on the map.

						📿 Search router 🚯 FeatureInfo 🔒 🔯 🖽 🍀
Parte	Search r	outer	No un X			
	Flurstücke	2				v s² s s s s s s s s s s s s s s s s s s
	Gemarkun	gsname				
\sum	Poppelso	lorf				Vile Richarg
	Gamarkun	repuip por				
7	/319	gsnunnner				
	4515					
heim	Flur					
	1					
K	Zähler					
	Nenner					
	*				Result	s: 379 3 39 Chateway 20 20 Turner (chate
T	Flur \$	Zähler \$	Nenner \$	Gemarkung 🖨	GemNr. \$	Germania 050 Balfingua
	1	39	3	Poppelsdorf	4319	Al Al Mandacave
PG	1	252	41	Poppelsdorf	4319	A4 Konigstraße
	1	472	48	Poppelsdorf	4319	B B B B B B B B B B B B B B B B B B B
	1	34	8	Poppelsdorf	4319	- Konigstraße
	1	558		Poppelsdorf	4319	Kontestade n 7 7 7 2 2
	1	351	53	Poppelsdorf	4319	
	1	323	49	Poppelsdorf	4319	
We					Search Reset	
1						Bonn Campus

Configuration

Note: Search Router needs access to the database where the search tables are. You have to define a new database configuration to be able to connect with the geo database. Read more about this at *YAML Configuration (Configuration and Application files)*.

The element may be integrated into the sidepane or with a *Button* into the toolbar.

Edit elem	ient	
Title	Search router	
Width*	700	\$
Height*	500	\$
Routes* +		A
Title*	Flurstücke	
Configuration*	class: Mapbender\CoreBundle\Component\SQLSearchEngine class_options: connection: alkis relation: qry_mb3_ax_flurstueck_suche	
Title*	Places	Ŵ
Configuration*	class: Mapbender\CoreBundle\Component\SQLSearchEngine class_options: connection: geodata_db relation: brd.qry_gn250_p_ortslage	
Title*	Lines	Ŵ
Configuration*	class: Mapbender\CoreBundle\Component\SQLSearchEngine class_options: connection: geodata_db relation: lines	
Title*	Polygon	Û
	Save Ca	ancel

• **Title:** Title of the element. The title will be listed in the Layouts section in the *Backend*. It is shown as sidepane tab/button title (usage in sidepane) or dialog title (usage via *Button*).

- Width: Width of the dialog (only for dialog, not sidepane).
- Height: Height of the dialog (only for dialog, not sidepane).

You can define Searches (Routes) with the button. Each Search has its own title that will show up in the search form in a selectbox. The definition of the search is done in YAML syntax in the textarea configuration.

- Routes: Collection of search routes.
- **Title**: Search Title (appears when a search is added to Routes by using),
- Configuration: Field to configure the search (appears when a search is added to Routes by using

```
+
).
```

Route Configuration

Here, you define all important information for each search:

- the database connection,
- the search tables/views and columns,
- the design of the form,
- and the design of the result table,
- the design of the results on the map.

```
class: Mapbender\CoreBundle\Component\SQLSearchEngine
class_options:
   connection: geodata_db  # database alias from doctrine.yaml
    relation: polygons # search table
    attributes:
                            # columns that are used in the form and in the result table
      - gid
     - name
     - type
     - city
   geometry_attribute: geom # reference to the geometry column
form:
    name:
        type: Symfony\Component\Form\Extension\Core\Type\TextType
       options:
           required: true
       compare: exact
    city:
        type: Symfony\Component\Form\Extension\Core\Type\TextType
        options:
           required: false
           label: City/Town
        compare: ilike
results:
    view: table
    count: true
```

(continues on next page)

```
exportcsv: true
sortBy: name
sortOrder: asc #desc
zoomToResultExtent: true
headers:
    gid: ID
    name: Name
    city: City/Town
callback:
    event: click
    options:
        buffer: 10
    minScale: null
    maxScale: null
```

Class and Class options

The configuration starts with the definition of the class (always class: Mapbender\CoreBundle\ Component\SQLSearchEngine) followed by the information about the database connection, definition of the search table, the columns that are used and the geometry column.

Form

In the form section, you can define the setup of the form and define textfields and selectboxes. You refer to the table columns and define the *type*, *options* and *compare*.

Туре

The form supports two types - *text* and *choice*.

You have to define a configuration for each table column you would like to provide in the search form. The configuraton starts with the column name (in the example it is the column called *name*).

- label: You can define a label parameter (if not defined, the capitalized column name will be used).
- **required**: You can define whether a type should be required (default is false). With required: true, a mandatory field is defined. That means that the user has to define a search term here before the search can run. Headings of required fields are marked with a red '*'.

You also can define the *Comparison*.

Type text

Type **text** allows you to provide text fields for your search formular.

Type text supports autocomplete. If you want to add autocomplete to the field you have to add additional parameters:

Supported autocomplete parameters are:

- data-autocomplete: 'on' parameter to activate autocomplete
- data-autocomplete-distinct: 'on' paramter to activate distinct autocomplete

- **data-autocomplete-using**: column1, column2 define other column/s that should be also considered on autocomplete
- **Type text** example with autocomplete:

Cities	~
Name*	
Bon	
Boniswil	^
Bonito	
Bonn	
Bonnac-la-Côte 😽	
Bonnanaro	
Bonnat	
Bonndorf im Schwarzwald	
Bonnefamille	
Bonnelles	
Bonnemain	~

form:	
name:	
<pre>type: Symfony\Component\Form\Extension\Core\Type\TextType</pre>	
→ # input box for text	
options:	
label: Name	
required: true	
attr:	
<pre>data-autocomplete: 'on' # activate autocomplete</pre>	
<pre>data-autocomplete-distinct: 'on' # only show equal results once</pre>	
data-autocomplete-using: type, city	
⇔comma seperated), WHERE input	
compare: exact	

Type choice

Type **choice** allows you to provide a selectbox in your search formular.

For type choice you can define a **placeholder**. This is a text that is shown before an option is selected.

You have to define the choices for the selectbox. You define a value and a key.

- **key**: will be send in the search query,
- **value**: is show as text in selectbox.

Note: From Mapbender 3.2 on onwards, you should use the value: key definition and use type: Symfony\Component\Form\Extension\Core\Type\ChoiceType.

type choice example with different selection options via dropdown:

User type					
Please select		~			
Please select					
Company					
Administration					
University	3				
User					

type:	
<pre>type: Symfony\Component\Form\Extension\Core\Type\ChoiceType</pre>	
↔ # box with selection options as dropdown list	
options:	
label: User type	
required: false	
<pre>placeholder: 'Please select'</pre>	
choices:	
Company: A	
Administration: B	
University: C	
User: D	
Something else: E	
compare: exact	

Comparison

For every field a comparison mode can be set. This is used by the engine when the query is sent. The following comparison modes are supported:

- exact: exact comparison (key = val)
- **iexact:** comparison ignoring cases (case-insensitive)
- like: Standard, both-side 'like'
- like-left: left-hand 'like'
- like-right: right-hand 'like'
- ilike: both-side 'like', (case-insensitive *searchstring*)
- ilike-left: left-side 'like' (case-insensitive *searchstring)
- ilike-right: right-side 'like' (case-insensitive searchstring*)

Result

In the section **results** the definition for the result table and styling is none.

```
results:
   view: table
   count: true
   exportcsv: true
   sortBy: name
   sortOrder: asc #desc
   zoomToResultExtent: true
   headers:
        aid: ID
       name: Name
       city: City/Town
   callback:
        event: click
        options:
            buffer: 10
            minScale: null
            maxScale: null
```

- view: is always set to table. No more options are possible.
- **count**: shows the number of results (default: true).
- exportcsv: generates a download button to give out the results as CSV file (default: false).
- **sortBy**: optional, define an attribute by attribute name the search results should be sorted by (default no sorting).
- **sortOrder**: optional, define how to sort the results ascending (asc) or descending (desc) (default: asc)
- zoomToResultExtent: define whether zoom to result should be activated (default: false).
- headers: definition of the columns to display and the alternative labeling.
- callback: define the action for the click event on a result item.
- **event**: only click is supported.

- buffer: zoom to the result item with a defined buffer.
- **minScale and maxScale**: zoom to the result item in a scale between minScale and maxScale.

Styling the Results

By default the results are shown in the default-OpenLayers Style.



You can overwrite this by handing over a styleMap-Configuration.

Three different styles are configured:

- **default**: default style
- select: style on select
- temporary: style on mouse-over

```
results:
   [...]
    styleMap:
        default:
            strokeColor: '#00ff00' # border color
            strokeOpacity: 1  # border opacity (1 - opaque / no transparency)
strokeWidth: 3  # border width
            fillColor: '#f0f0f0' # fill color
            fillopacity: 0# fill opacity, (0 full transparency)pointRadius: 6# size of the point symbol
            label: ${name} - ${gid} # Attribut to use for labeling or fiexed text
            fontColor: "#ff0000" # font color
fontSize: 30nx # font size
                                     # font size in piexels
            fontSize: 30px
            fontFamily: 'Arial, Courier New, monospace'
            fontWeight: bold # font weight
            labelOutlineColor: '#ffff00' # font outline
            labelOutlineWidth: 1 # font outline width
            fontOffsetX: -18
                                   # Offset X-axis
            fontOffsetY: -18
                                     # Offset Y-axis
        select:
            strokeColor: '#0000ff'
            strokeOpacity: 1
            strokeWidth: 4
            fillColor: '#ff00ff'
            fillOpacity: 0.8
            pointRadius: 10
            label: ${name}
        temporary:
           strokeColor: '#0000ff'
           fillColor: '#0000ff'
```

(continues on next page)
(continued from previous page)

fillOpacity: 1
label: 'fixed Text'

In the default style the point-symbol interior is transparent (fillOpacity: 0). Only their outlines will be drawn in green. The selected features will be drawn with a purple fill and an opacity of 0.8. The outline of the symbol is blue. The temporary symbols on mouse-hover are blue points.



The styleMap settings override the default settings, so you only have to define the sections you want to overwrite. No extra styleMap is set the default style will be used.

Note: Note that the hexadeximal color values have to be stated in quotation marks, because # would be interpreted as a comment instead.

Configuration Examples

1. Example

+

In this example, a search was configured for the Mapbender user and added into the sidepane with

in the Layouts. Sidepane * Title Type +

The confguration dialogue for this example looks like this:

Edit element			*
Title*	Search router		^
Target	Мар	~	
Dialog*			
Timeout factor*	3	۲	
Width*	700	۲	
Height*	500	۲	
Routes*			
+			
Title*	Mapbender User	×	
Configuration*	class: Mapbender\CoreBundle\Component \SQLSearchEngine class_options: connection: demo relation: mapbender_user	~	~
		Update Car	ncel

The element title (*Title*) is Search. It is again displayed as a title in the sidepane. The checkbox is unchecked, because the element is implemented into the sidepane and not as a button. The *Timeout factor* is set to 2. The fields *Width* and *Height* are filled, but they won't be used in this application, be-

cause the element is configured in the sidepane. It is implemented via the and *Routes* into the search, called (*Title*) Mapbender User. The yaml-Configuration of the Element is written in *Configuration*. Here is the complete configuration:

class: Mapbender\CoreBundle\Component\SQLSearchEngine

(continues on next page)

+

(continued from previous page)

```
class_options:
                                         # database (on which the element has access)
  connection: geodata_db
  relation: mapbender_user
                                         # table (on which the element has access)
 attributes:
                                         # table columns (which the element addresses)
    - gid
    - orga
    - town
    - usertype
                                         # definition of the geometry column
 geometry_attribute: the_geom
form:
                                         # configuration of the form
                                         # search field (e.g. search for specific Mapbender User)
 orga:
    type: Symfony\Component\Form\Extension\Core\Type\TextType
    options:
     required: false
                                         # no mandatory field
     label: 'Mapbender User'
                                         # caption of the search field
     attr
                                         # additional definable attributes
        data-autocomplete: 'on'
                                         # auto-completion of search words
        data-autocomplete-distinct: 'on'
    compare: ilike
                                         # see section 'comparison mode' on this page
  town:
                                         # search field (e.g. search for specific city)
   type: Symfony\Component\Form\Extension\Core\Type\TextType
    options:
     required: false
                                         # no mandatory field
     label: City
                                         # caption of the search field
     attr:
        data-autocomplete: 'on'
        data-autocomplete-distinct: 'on'
   compare: ilike
                                         # search field (search for specific User type)
  usertype:
    type: Symfony\Component\Form\Extension\Core\Type\ChoiceType
    options:
     placeholder: 'Please select...'
                                         # displayed text in field before entering a search
     choices:
                                         # choices need to have the following format: "entry in the
→ database column": "displayed name in the drop down list"
       1: Company
       2: Administration
       3: University
       4: User
     required: false
                                       # no mandatory field
     label: User type
                                        # caption of the search field
                                        # see section 'comparison mode' on this page
   compare: exact
                                         # configuration of the shown results list
results:
  view: table
                                         # display results as table
  count: true
                                         # show number of results
 headers:
                                         # column title; format: column title in the database: column
\rightarrow title shown in the table
   gid: ID
   orga: 'Mapbender User'
   town: City
  callback:
   event: click
    options:
     buffer: 10
     minScale: null
     maxScale: 10000
  styleMap:
                                         # Styling points on the map
```

(continues on next page)

	(continued from previous page)
<pre>default: strokeColor: '#003366' strokeOpacity: 1 fillColor: '#3366cc' fillOpacity: 0.5</pre>	# Styling of all points on the map
<pre>select: strokeColor: '#330000' strokeOpacity: 1 fillColor: '#800000' fillOpacity: 0.5</pre>	# Styling of the selected point on the map
<pre>temporary: strokeColor: '#0000ff' fillColor: '#0000ff' fillOpacity: 1</pre>	

This picture illustrates which consequences the configurations in the yaml-definition have for the search formula:



Displayed is the excerpt of the yaml-definition configuring the formula. Columns *orga*, *town* and *usertype* are used in the formula and implemented as the fields *Mapbender User*, *Town* and *Usertype*. *Mapbender User* and *Town* are type text, *Usertype* can be of various types.

A complete search for the Mapbender User WhereGroup, in the Town Bonn, of the Usertype Company and the found results will look like this:

		- 1/5
Suchen		
Mapbender User		• 7
Mapbender User		
WhereGroup		
Stadt		
Bonn		
Nutzertyp		
Company		• []
	Suchen Zurücksetz	2N Cors durillers
	Ergebniss	ie: 2
ID Mapbender User	Stadt	
323 WhereGroup	Bonn German	
899 WhereGroup GmbH & Co	.KG N Bonn	vin
	M2	
		77-

This picture illustrates the consequences our configuration of the yaml-defnition had on the display of the results.

		results:
		view: table
	Ergobnisso: 2	count: true
	Ligeonisse. 2	headers:
ID Mapbender User	Stadt 🗲	gid: ID
323 WhereGroup	Bonn Germany	orga: 'Mapbender User
	2	town: Stadt
whereGroup GmbH & Co. KG	Boun	callback:
	~	event: click
		options:
		buffer: 10
		minScale: null
		maxScale: 10000
		styleMap:
		4 Vdefault:
		strakeColor: L#00336
		StrokeColor: #00336
		strokeColor: #003360 strokeOpacity: 1
		strokeColor: #00336 strokeOpacity: 1 fillColor: '#3366cc'
		strokeColor: #00336 strokeOpacity: 1 fillColor: '#3366cc' fillOpacity: 0.5
		strokeColor: #00336 strokeOpacity: 1 fillColor: '#3366cc' fillOpacity: 0.5 select:
		strokeColor: #00336 strokeOpacity: 1 fillColor: '#3366cc' fillOpacity: 0.5 select: strokeColor: '#33000
		strokeColor: #00336 strokeOpacity: 1 fillColor: '#3366cc' fillOpacity: 0.5 select: strokeColor: '#33000 strokeOpacity: 1
		strokeColor: #00336 strokeOpacity: 1 fillColor: '#3366cc' fillOpacity: 0.5 select: strokeColor: '#33000 strokeOpacity: 1 fillColor: '#800000'

Here, only the configuration of the results is shown. The number of results is shown because count: true is enabled. The titles of the columns are defined in *headers*. Here, the name of the column is mentioned first, to define which results are referenced. After the colon, we set the title which will be displayed in the application.

In the block *styleMap*, the points are styled. The block *default* references all points, and the block *select* only selected points.

Because none of these fields are mandatory, the search will work wih only on field.

2. Example

The following example uses the german geographical names data in 1:250.000 from the Bundesamt für Kartographie und Geodäsie. The data was extracted to gn250_p table in the gisdb database and can be used for the search. The data has some specific columns:

- **id**: the id of the dataset
- name: the name of the dataset
- kreis: the administrative county (not for every dataset)
- **oba_wert**: the type of data (e.g. station, museum, etc.)

Example of a route configuration in the configuration area:

```
class: Mapbender\CoreBundle\Component\SQLSearchEngine
class_options:
 connection: geodata_db
  relation: gn250_p
  attributes:
    - id
    - name
    - kreis
    - oba_wert
 geometry_attribute: geom
form:
  name:
    type: Symfony\Component\Form\Extension\Core\Type\TextType
    options:
      required: true
    compare: ilike
results:
 view: table
  count: true
  exportcsv: true
  sortBy: name
  sortOrder: asc
  zoomToResultExtent: true
 headers:
   id: TD
   name: Name
   kreis: Landkreis
   oba_wert: Art
  callback:
    event: click
    options:
      buffer: 10
```

(continues on next page)

(continued from previous page)

<pre>minScale: null</pre>			
<pre>maxScale: null</pre>			

YAML-Definition

This template can be used to insert the element into a YAML application.

```
target: map
                                                           # ID map element
asDialog: true
                                                           # true: results in dialog box
timeoutFactor: 3
                                                           # timeout factor (multiplied by autocomplete
\leftrightarrow deceleration) to prevent autocorrect after a search has been started
height: 500
                                                           # height of dialog
width: 700
                                                           # width of dialog
routes:
                                                           # collection of search routes
                                                           # machine-readable name
   demo_polygon:
    class: Mapbender\CoreBundle\Component\SOLSearchEngine # path to used search engine
   class_options:
                                                           # options passed to the search engine
       connection: geodata_db
                                                           # search db, DBAL connection name, ~ for
\rightarrow default
       relation: polygons
       attributes:
           - gid
                                                           # list of columns, expressions are possible
           - name
           - type
           - citv
                                                           # name of the geometry column, attention:
       geometry_attribute: geom
\rightarrow projection needs to match with the projection of the map element
  form:
                                                           # declaration of the search form
                                                           # field name, column name
       name:
           type: Symfony\Component\Form\Extension\Core\Type\TextType
                                                                             # input field, normally
→ text or numbers
           options:
                                                           # declaration of the input field
               required: false
                                                           # HTML5, required attributes
               label: Name
                                                           # custom label, otherwise field name used
               attr:
                                                           # HTML5, required attributes
                   data-autocomplete: on
                                                          # attribute to activate autocomplete
                   data-autocomplete-distinct: on
                                                          # attribute to activate distinct autocomplete
                   data-autocomplete-using: type
                                                          # autocomplete, list of input fields (with
→comma seperated), WHERE input
                                                           # see section 'comparison mode' on this page
           compare: ilike
       city:
           type: Symfony\Component\Form\Extension\Core\Type\TextType
           options:
               required: false
               label: City/Town
           compare: ilike
       type:
           type: Symfony\Component\Form\Extension\Core\Type\ChoiceType
           options:
               placeholder: Please select a type.
               required: false
               choices:
                   A Company: A
                   B Administration: B
                   C University: C
```

(continues on next page)

(continued from previous page)

```
D User: D
                  E Something else: E
  results:
      view: table
                                                            # display results as table
                                                            # show number of results
      count: true
      exportcsv: true
                                                            # column title
      headers:
          gid: ID
                                                            # column name -> header
          name: Name
          type: Type
          city: City/Town
      callback:
                                                            # click event
          event: click
                                                            # click or mouseover event
          options:
              buffer: 10
                                                            # buffer (before zoom)
              minScale: ~
                                                            # scaling boundaries for zoom, ~ for nol
→boundaries
              maxScale: ~
      styleMap:
          default:
              strokeColor: '#00ff00'
              strokeOpacity: 1
              fillOpacity: 0
          select:
              strokeColor: '#ff0000'
              fillColor: '#ff0000'
              fillOpacity: 0.4
          temporary:
              strokeColor: '#0000ff'
              fillColor: '#0000ff'
              fillOpacity: 1
```

3.4.2 Simple Search

Simple Search offers a single field search or keyword search. The search query is transmitted to a search service. The search servers Apache Solr, Nominatim, photon or an OGC API Features service can be used.

An input field is offered which can be integrated directly into any region. Added to content you have to define the position. Simple Search sends the entered search term to a configurable URL and receives JSON-formatted data, which contain a label and geometry attributes for each entry.

The geometry data can be encoded in WKT or GeoJSON format.

It is configurable which information from the result json should be shown as result

βimple Search	Q
---------------	---

Edit elem	ent
Title	Simple Search
Placeholder	
Query URL *	https://photon.komoot.io/api/?limit=20&⪫=50.739&lon=7.08428
Query URL key *	q
Query Whitespace replacement pattern *	
Query key format *	%s
Token (JavaScript regex)	[^a-zA-Z0-9äöüÄÖÜß]
Token search (JavaScript regex)	([a-zA-ZäöüÄÖÜß]{3,})
Token replace (JavaScript regex)	\$1*
Collection path	features
Label attribute *	<pre>\${properties.name} \${properties.street} \${properties.housenumber} (\${propert</pre>
Geom attribute *	geometry
Geom format *	GeoJSON 🗸
Source SRS	EPSG:4326
Delay *	300
Result buffer *	5
Result minscale *	100
Result maxscale *	1000
Result icon url *	/bundles/mapbendercore/image/pin_red.png
Result icon offset *	-6,-32
	Save Cancel

- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Position:** Position (only when used in Map area). Options: 'left-top', 'right-top', 'left-bottom', 'rightbottom'
- **Placeholder:** Text to display when the search fiels is empty. If a placeholder is not defined, the content of the title is used instead.
- **Query URL:** Solr URL for the search (e.g. http://localhost:8080/solr/core0/select? wt=json&indent=true) or Nominatim URL.
- Query URL key: The query parameter key to append (e.g. q).
- Query Whitespace replacement pattern: Pattern for replacing white spaces.
- **Query key format:** Simple search format (e.g. %s).
- Token search/replace (JavaScript regex): Tokenizer split/search/replace regexp.
 - Token, e.g.: [^a-zA-Z0-9äöüÄÖÜß]
 - Token search, e.g.: ([a-zA-ZäöüÄÖÜß]{3,})
 - Token replace, e.g.: \$1*
- **Collection path:** Can be a dotted attribute path to extract from the query result (e.g. response. docs).
- Label attribute: Name of the attribute/s to show as result.
- Geom attribute: Name of the geometry data attribute (e.g. geom).
- Geom format: Geometry data format, can be WKT or GeoJSON (e.g. WKT).
- Source SRS: EPSG code of the spatial reference system (e.g. EPSG: 25832)
- Delay: Autocomplete delay. Use 0 to disable autocomplete (e.g. 300).
- **Result buffer:** Buffer result geometry with this (map units) before zooming (e.g. 10).
- Result minscale/maxscale: Scale restrictions for zooming, ~ for none (e.g. 1000 und 5000).
- Result icon url: Icon to display as result marker (e.g. /bundles/mapbendercore/image/pin_red.png).
- **Result icon offset:** Offset x and y for the icon (e.g. 0,0).

Duplicate a search configuration

The element can handle multiple search configurations. It is possible to duplicate a search form in the backend configuration window with the Copy button:

Edit elem	ent	
Title	mb.core.simplesearch.class.title	
Configurations* +		
Parcel Search		≉ (R û
Address Search		\$ () 1
Title*	Address Search	0
Placeholder		0
Query URL*	http://geodaten.metropoleruhr.de/suche?wt=json&indent=true&ro	0
Query URL parameter key*	q	Θ
Query Whitespace replacement pattern		ø
Query key format*	%s	0
Tokenizer: Split Regex	[^a-zA-Z0-9äöüÄÖÜß]	0
Tokenizer: Search	h ([a-zA-ZäöüÄÖÜß]{3,})	θ
	Sav	Cancel

Use drag and drop to sort the different search configurations for the application list.

There, they are selectable via a dropdown menu next to the search bar:

Address Search		\sim	Q
	Parc Sear	el ch	
	Add Sear	ress ch	

Flexible configuration via label_attribute

The result JSON provides different information. It is possible to define one or several attributes for the result text.

label_attribute: label

The definition is relative to the Collection path. It is possible to use additional text to separate the attributes.

```
label_attribute: '${properties.address.city} ${properties.address.road} ${properties.address.house_

→number}'
```

label_attribute: 'Town: \${properties.address.city}: \${properties.address.road} - \${properties.address. →house_number}'

YAML-Definition

<pre>placeholder: 'please search'</pre>	# Text to display
\rightarrow when the search fiels is empty. If a placeholder is not defined, the content of	the title is used.
anchor: 'right-bottom'	<pre># Position (only</pre>
→when used in Map area). Options: 'left-top', 'right-top', 'left-bottom', 'right-	bottom'
<pre>query_url: http://example.com/solr/core/0/select?wt=json&indent=true&rows=8</pre>	# Example Solr URL
→(e.g. ``http://localhost:8080/solr/core/0/select?wt=json&indent=true``) or Nomin	atim URL.
query_key: q	# The query <mark>l</mark>
⇔parameter key to append	
query_ws_replace:	# Pattern for
\leftrightarrow replacing white spaces.	
<pre>query_format: '%s'</pre>	# Simple search
\hookrightarrow format.	
token_regex: [^a-zA-Z0-9äöüÄÖÜß]	# Tokenizer split
⇔regexp.	
<pre>token_regex_in: ([a-zA-ZäöüÄÖÜß]{3,})</pre>	# Tokenizer search
⇔regexp.	
<pre>token_regex_out: '\$1*'</pre>	# Tokenizer replace
⇔regexp.	
<pre>collection_path: response.docs</pre>	# Can be a dotted
\hookrightarrow attribute path to extract from the query result.	
label_attribute: label	# Name of the
→attribute to use for entry labeling	

(continues on next page)

	(continued from previous page)
<pre>geom_attribute: geom</pre>	# Name of the
→geometry data attribute	
geom_format: WKT	# geometry data
\hookrightarrow format, can be WKT or GeoJSON	
sourceSrs: 'EPSG:25832'	# Projection of the
⇔result data	
delay: 300	
result:	<pre># Autocomplete delay.</pre>
→ Use 0 to disable autocomplete.	
buffer: 50	# buffer result
→geometry with this (map units) before zooming	
minscale: 1000	<pre># scale restrictions</pre>
⇔for zooming, ~ for none	
maxscale: 5000	<pre># scale restrictions</pre>
⇔for zooming, ~ for none	
<pre>icon_url: /bundles/mapbendercore/image/pin_red.png</pre>	# icon to display as
⇔result marker	
<pre>icon_offset: -6,-38</pre>	# Offset x and y for
→the icon	

Set-up of Solr

- Download: https://solr.apache.org/downloads.html
- Documentation: https://solr.apache.org/guide
- Quickstart: https://solr.apache.org/guide/solr-tutorial.html

Set up of Nominatim

- Download: http://nominatim.org/release-docs/latest/admin/Installation/
- Documentation: http://nominatim.org/release-docs/latest/

Set up of photon

photon is an open source geocoder built for OpenStreetMap data.

• Download & Documentation: https://github.com/komoot/photon

Set up of OGC API Features

Several projects support OGC API Features like QGIS, GeoServer, pygeoapi.

HTTP Callbacks

• /search: Widget proxy which then queries configured URL. In dev-mode the final query URL will be returned as a x-mapbender-simplesearch-url header for easier debugging.

3.4.3 Routing

The routing element adds a routing tool to an application. After specifying the start, destination and any intermediate points, a suitable route is displayed on the map. Information about the route can also be displayed.



Edit element			
Advanced route	Advanced route settings		
Element			
Title	Routing		
🗌 Route immediately 🛛 Illow intermediate points			
🕑 Enable Search			
Zoom buffer	150		
(m)*			
Line color	rgba(66,134,244,1)		
Line width	3		
Route info text	${\text{start}} \rightarrow {\text{destination}} < /br> {\text{length}} / {\text{time}}$		

- Advanced route settings: Allows you to make further settings (default: false).
- Title: Elements Title.
- **Route immediately:** Configuration to deactivate/activate automatic routing without the users interaction (default: false).
- Allow intermediate points: Configuration for deactivating/activating intermediate points (default: false).
- Enable Search: Configuration to deactivate/activate the search option (default: false).
- Zoom buffer (m): Definition of a zoom buffer for the result display in meters (default: 0).
- **Line color:** Option to adjust the line color and opacity with the rgba standard (default: rgba(66, 134, 244, 1)).
- Line width: Option to adjust the line width (default: 3).
- Route info text: Option to add an info text for the rout (default: {start} [] {destination} </br>
 will take {time}).

Path start icon	/bundles/mapbenderrouting/image/start.png
Size start icon w, h	
Offset start icon x, y	
Path intermediate icon	/bundles/mapbenderrouting/image/intermediate.png
Size intermediate icon w, h	
Offset intermediate icon x, y	
Path destination icon	/bundles/mapbenderrouting/image/destination.png
Size destination icon w, h	
Offset destination icon x, y	

- Path start icon: Customize the start icon (default: /bundles/mapbenderrouting/image/start.png).
- **Path intermediate icon:** Customize the intermediate icon (default: /bun-dles/mapbenderrouting/image/intermediate.png):
- **Path destination icon:** Customize the destination icon (default: /bun-dles/mapbenderrouting/image/destination.png).
- **Size Icon:** Adjust the size of the different icons.
- **Offset Icon:** Adjust the offset of the different icons.

Routingso	oftware
Routing software*	OSRM
URL	https://routing.openstreetmap.de/routed-%profile
Services*	Route
Transportation mode	Car Bike Foot
API-Version*	v1
Route description*	yes
Attribution	Daten © <a class="link-
primary" href="https://www.openstreetmap.org/copyright">OpenStreetMap -Mitwirkende (<a class="link-primary" href="https://
opendatacommons.org/licenses/odbl/index.html">ODbL), CO BY-SA , <a class="link-
primary" href="https://openstreetmap.org/fixthemap">mitmachen/Fehler melden

- Routing software: Select the routing software (OSRM).
- URL: Set the URL address for the routing software or choose a variable, e.g. https://routing. openstreetmap.de/routed-%profile (default: https://).
- Services: Select from various services (defaut: Route).
- **Transportation mode:** Select the routing profiles (car, bicycle, pedestrian). It is also possible to select more than one (default: none).
- **API-Version:** Determine the version of the API (default: v1).
- **Route description:** Select whether there should be a route description or not (default: no).
- Attribution: Provide a source reference (default: Take a look at the screenshot above).

Search	
Search software*	Solr
Search URL*	https://osm-photon-search.wheregroup.com/search/api?limit=20⪫=50.7163&lon=
Search parameter key*	q
Whitespace replacement pattern	
Search format	%s
Tokenizer split	[^a-zA-Z0-9āöüÄÖÜß]
Tokenizer search	([a-zA-ZäöüÄÖÜß]{3,})
Tokenizer replace	\$1*
Collection path	features
Label attribute *	\${properties.name} \${properties.street} \${properties.housenumber} \${properties.cit
Geom attribute*	geometry
Geom format*	GeoJSON
Projection Geom*	EPSG:4326
	Save

- Search software: Select the search service (default: Solr).
- **Search URL:** Set the URL address for the search software.
- Search parameter key: Set the search parameter key (default: q).
- Whitespace replacement pattern: Set parameters to replace the search term.
- **Search format:** Set the search format (default: %s).
- Token split/search/replace (JavaScript regex): Tokenizer splits/searches/replaces regexp.
 - Token split, z.B.: [^a-zA-Z0-9äöüÄÖÜß]
 - Token search, z.B..: ([a-zA-ZäöüÄÖÜß]{3,})
 - Token replace, z.B..: \$1*
- **Collection path:** Set the attribute path that is extracted from the query result (default: response.docs).
- Label attribute: Name of the attribute's to show as result (default: label).
- Geom attribute: Name of the geometry attribute (default: geom).
- Geom format: Geometry data format, can be WKT or GeoJSON (default. WKT).
- Projection Geom: EPSG code of the spatial reference system(default EPSG:4326).

YAML-Definition

3.5 Share elements

3.5.1 Share elements (Overview)

Mapbender offers multiple functions that simplify collaborative work within applications.

- Share URL enables quick sharing of self-configured map states via URL,
- View Manager stores custom map states,
- Application Switcher enables easy cross-application switches,
- *Persistent map view* enables the map state to be saved in the browser.

Moreover, certain map view parameters are automatically passed in every application URL. This allows users to share specific map views via URL.

Contained view parameters include:

- center
- scale
- rotation
- spatial reference system

There is no extra configuration for this functionality. It is always turned on.

If a URL is opened up in a new browser tab, previously mentioned view configurations will be restored. Made changes can be undone/redone with the browser back/forward buttons. Users will be sent back to the same part of the map if they refresh the page. They will not be sent back to the configured initial map view. In order to do so, users have to open the application again from the application list or manually delete the hash part of the application URL.

Note: Attributes that are not saved are the temporary layer selection and layer sorting, geometry features, source additions via the WMS loader or other runtime additions.

3.5.2 Share URL

URL sharing can be further simplified by integrating a respective element in the toolbar or footer.



After clicking on the button, the URL is saved to the clipboard. Default browser interactions (e.g. open in new tab) are also possible.

This element stores the following information:

- basic view parameters (center, scale, rotation, SRS)
- layer and layerset settings changes (selected / deselected layersets, sources and layers, layer opacity settings)

Note: The URL does not transfer dynamically added sources (via WmsLoader), dynamically removed layers or sources (via Layertree context menu) or changes to the source or layer order (via Layertree drag&drop)

Add element Top toolbar - Share URL			
✓ Show label			
Title	Share URL		
Tooltip			
	Back Add Cancel		

- Show label: Enables or disables text (title) next to the button (default: true).
- **Title:** Title of the element.
- Tooltip: Text to use as tooltip.

YAML-Definition

This template can be used to insert the element into a YAML application.

3.5.3 View Manager

View Manager stores and reapplies custom map states. These contain the following map parameters:

- Center
- Layers of Sources
- Selected *Layerset*
- Rotation
- Scale
- Source opacities
- SRS

Saved states are always reapplied on top of the current configuration. This means that changed application configurations will remain in effect even after reloading the page.

Enter title		8
Save as public		
Title	Date	fter
Map State 3	2021-06-14	8 🖻 占
Map State 2	2021-06-14	805
Map State 1	2021-06-14	B 🖻 🍃

Note: Thus far, View Manager can only be implemented in the Sidepane.

Basic operations

Each state must be given a title for reidentification. For saving the current map view as a new state, enter a title and click on the adjoined save button.

resq			B
] Save as	public		
Title	Date		
Test	2021-06-14	B	ŵ ►

The most basic interaction (always available) is re-applying the map state stored in the entry. This option is always on: The saved map state will be reapplied as soon as "Apply" is hit on the selected map state in list view. Moreover, entries may offer a "Replace" interaction. This will overwrite the map state stored in the entry, and will also update the title, using the global title input field. Also, entries may offer a "Delete" interaction (with an extra confirmation step).

The View Manager does **not** store or reapply the following configurations:

- any interactively added sources (via WMS Loader)
- any interactively removed layers (via *Layertree* context menu)
- any values for WMS dimensions
- any dynamically rendered geometries (Digitizer etc.)

Access rights

Each map state is attributed to an application and further separated into a public and user-private list. The rights to save, reapply or delete map states are defined in the element configuration. Furthermore, rights to show private lists and dates as well as the permission for anonymous users to save map states can be set here.

In general, access checks on public entries are suspended for the root user. The administrator can create, update and delete public entries at will.

Anonymous users are excluded from working with private entries and they can never delete public entries. Their ability to create and update public entries is gated through the "Allow saving to anonymous users" option. If this checkbox is deactivated, their access to public entries is downgraded to read-only. If the goal is to exclude anonymous visitors completely, a ROLE_USER access restriction has to be set on the entire element.

Add element Sidepane - View manager			
Title	View manager		
✓ Show private list			
Show date			
Allow saving to anonymous users			
Public list	Do not show 🗸		
Note: the admin	histrator can always delete public entries.		
	Back Add Cancel		

YAML-Definition

This template can be used to insert the element into a YAML application.

viewmanager:	
title: View Manager	# Title of the element
<pre>class: Mapbender\CoreBundle\Element\ViewManager</pre>	# Path to element class
publicEntries: rw	# String or empty (falsy value disables public
→entries entirely); other allowed values are ro (read only), rw (allow read and write), rwd (allow
\hookrightarrow read and write and deletion) (default: ro).	
privateEntries: true	# Turns user-private states on, with full usage
→(save, reapply, delete) (default: true).	
allowAnonymousSave: true	# Extend right to save public entries also to
⊶anonymous users (default: false).	
<pre>showDate: true</pre>	# Show date of creation or last update in entry
→listing (default: true).	

3.5.4 Application Switcher

The Application Switcher provides a selectbox that refers to other Mapbender applications. You can switch from one application to another. The map extent will be preserved.



Edit element			
Title	Application switcher		
Applications*	Mapbender Demo Mapbender Basic Demo Mapbender Mobile Demo Basic Demo		
🗌 Open in new ta	ab		
	Save Cancel		

- Title: Title of the element. The title will be shown as tooltip on mouseover on the selectbox.
- **Applications:** Choose the applications that should be offered in the selectbox.
- **Open in new tab:** Define whether the new application should be opened in the same window (default) or in a new tab.

YAML-Definition

This template can be used to insert the element into a YAML application.

```
title: Choose an Application  # Text will be displayed as tooltip
class: Mapbender\CoreBundle\Element\ApplicationSwitcher
applications: ["mapbender_user", "mapbender_user_basic"]  # Define the applications for the
ApplicationSwitcher as array
open_in_new_tab: true  # false/true open application in new tab
```

3.5.5 Persistent map view

This feature makes certain view parameters and certain source settings persistent. This enables an application to be closed and opened up again in the same browser without losing certain information.

Persisted and restored settings encompass:

- view parameters (center, scale, rotation, SRS)
- per-layerset selected or deselected states
- per-source and source layer selected or deselected states
- per-source opacity

Note: Persistence is purely based on local browser storage, which means it is private to a user's local browser. It also remains private for multi-user systems. There is no interaction whatsoever with the Mapbender login.

Not-supported map view parameters are:

- Dimension parameter values
- Source additions (via WMS Loader)
- Layer / entire source removals (via Layertree context menu)
- Source / layer reordering operations via Layertree (via drag&drop)
- States of per-layer featureinfo checkboxes

Configuration

Persistent map view is enabled on a per-application basis with a new checkbox under the "Base data" tab.

Base data Layouts Layersets CSS Security	View
Title * Demo	
URL Title * mapbender_user_yml	
Thumbnail Select file screenshot.png	and the second s
Map engine *	
Description	, ,
Full desktop application showing most of the standard Mapbender elements	
Persistent map state	

This change introduces a new column in the *mb_core_application* table and therefore requires *bin/console doctrine:schema:update –force* to be run.

YAML-Definition

This template can be used to insert the element into a YAML application with a new *persistentView* entry on the top level. Omitting this entry is the same as setting it to false.

```
parameters:
    applications:
        mapbender_user:
        title: Mapbender Demo Map
        screenshot: screenshot.png
        published: true
        persistentView: true  # parameter to activate Persistent map view
        template: Mapbender\CoreBundle\Template\Fullscreen
```

3.6 Other

3.6.1 About Dialog

This element creates a *Button* which shows a simple about dialog, listing the version of your Mapbender installation. The button can be placed into the toolbar and the footer region.



Add element Map area - About dialog			
Show label			
Title	About dialog		
Tooltip	mb.core.aboutdialog.admin.tooltip		
	Back Add Cancel		

- **Show Label:** Enable/Disable About dialog text next to its icon (default: true).
- **Title:** Text indicated next to the about dialog icon.
- **Tooltip:** Text to use as a tooltip. Appears when hovering over the icon.

YAML-Definition

This template can be used to insert the element into a YAML application.

title: 'About Mapbender'# text indicated next to the about dialog icon.tooltip: 'About Mapbender'# text to use as tooltiplabel: true# false/true to label the button, default is trueicon: 'icon-about'# icon to display on button

3.6.2 Button

The button element provides a push button widget. Some elements like *Legend*, *Layertree*, *FeatureInfo*, *Line/Area Ruler* and *PrintClient* need a button to be displayed/activated if not defined in a frame.

Buttons optionally can be grouped, so that only one button in a group can be active at any given time. This is done by the group paramter. You can define a button that refers to a website or script using the click paramter. You can only choose features as target parameter, which have been added in the Map area or footer before.

Add element Footer - Button			
🖌 Show label			
Title	Button		
Target*	Choose one	~	
Group			
Tooltip			
lcon	None	~	
		Back Add Cancel	

- Show label: Enables or disables text (title) next to the button (default: true).
- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Target:** Target element (Title(ID)) of the button. The target element will be triggered by clicking on the button (e.g. Print).
- **Group:** Adds the element to a group. Only one button of the group may be activated.
- **Tooltip:** Text, that will be indicated if the mouse hovers over the button for a longer time.
- Icon: Symbol of the button. Based on a CSS class.

Icons

For some symbols you can choose between two different types of icons:

- A symbol based on a graphic (e.g. "About"),
- A symbol based on a font (e.g. "About (Font Awesome)").

The latter are based on a IconSet, which is delivered with Mapbender as a module. We recommend to use the symbols from this library.

Hint: It is also possible to deactivate an icon set and/or to use other icons. For more, see *Customizing icons*.

More information on icons under:

- https://github.com/mapbender/icons
- http://rawgit.com/mapbender/icons/master/demo.html

Configuration examples:

Depending on the purpose of the application, different buttons are required which provide different features. These can be integrated as needed. You can add buttons for features which are integrated in the Map area. For example, the legend or the line and/or area ruler can be activated or opened with buttons:

Button for the legend element

The legend is very helpful because it provides information about the Map area. In this user example, the legend is integrated in the Map area. You can find a descripton of how to configure the legend element in this documentation under *Legend*. You can add a button for the legend by following these steps:

First, you have to select the button element by clicking on tab.	т	in the Toolbar section in the Layouts
Top toolbar		\$

1

Title

Туре +

After the selection of the button element, the "Add element - Button" dialog box opens, where you can configure the button.

You can set the name of the legend button in the field *Title*. Here the title is "Legend". There will be no text displaced during hovering over the button, because no text was defined in the field *Tooltip*. You can choose from a variety of icons to set the icon for your button. In this example, the icon "Legend" was chosen.

Add eler	nent ^{ton}	
Show label		
Title	Legend	
Target*	Legend	~
Group		
Tooltip		
lcon	None The Information Information (inverted)	~
	Eagend	
	 ➢ Line ruler ☑ List ☑ Logout 	
		Back Add Cancel

In the *Target* field you can choose the predefined feature which should be activated or opened by clicking on the button. The dropdown list contains all features which have been added to the Map area, the sidepane or the footer before. In this example, the option "Legend" was chosen.
Add element Top toolbar - Button		
Show label		
Title	Legend	
Target*	Legend ~ FeatureInfo	
Group	Image export	
Tooltip	Legend	
lcon	POI	
	Print	
	Scale bar	
	Back Add Cancel	

In this example, Group remains empty. In the Mapbender application, the button will look like this:



The title of the element is displayed next to the icon, because in the configuration dialog box the option "Show label" was checked. If the checkmark is not set, the button looks like this:



If you choose the *lcon* "List" instead of "Legend" and check the option "Show label", the button would look like this:



Now, by clicking on the button, the legend will open in a dialog box.

Button for Line and Area Ruler

The line and area ruler also can be integrated in the application via buttons. These elements must have been added to the Map area, sidepane or footer in order to do so.

This example demonstrates how to create groups: Both buttons should be in one group, so that only one line or area ruler can be active and not both at the same time.

Edit element		
Show label		
Title	Line	
Target*	Line	
Group	measure	
Tooltip		
lcon	Line ruler	
	Save Cancel	

In this example, the *Title* of the button is "Line". The element references to a *Target* called "Line". This element was created beforehand with the feature Line/Area Ruler. You can find a description on how to

create this feature under *Line/Area Ruler*.

To group this button and the button for the area ruler, you have to put a group name in the field *Group*. In this example, the name of the group is "measure". You also have to add this group name to the button for the area ruler.

The button for the area ruler can be integrated the same way as the button for the line ruler. The dialog box for the configuration of this button can look like this:

Edit element		
Show label		
Title	Area	
Target*	Area	
Group	measure	
Tooltip		
lcon	D₂ Area ruler ✓	
	Save Cancel	

Attention should be paid to the field *Group* with the group name "measure". It has to be the same as the one of the button line ruler. Both buttons can look like this in the application:



If the button line ruler is active, it looks like this:



As soon as you click on the button area ruler, the feature line ruler is deactivated and the feature area ruler activated.

YAML-Definition

This template can be used to insert the element into a YAML application.

title:	# title
tooltip:	# text to use as tooltip
icon: ~	# icon CSS class to use
label: true	<pre># false/true to label the button, default is true</pre>
target: ~	# title (Id) of target element
click:	<pre># refer to a website or script like http://mapbender.org</pre>
group: ~	# group to put the button into. Only one button per group can be active
action: ~	<pre># method of target to call when button is activated</pre>
deactivate: ~	<pre># method of target to call when button is deactivated</pre>

3.6.3 Cookie Banner

Applications support displaying a cookie banner which is customized via the Mapbender configuration file parameters.yaml. We use the code from Cookie Consent without making an additional call to the internet.

The banner is displayed in any application on the first run.



After this banner is dismissed it doesn't appear again until you have deleted the cookie in your web browser. Mapbender depends on cookies and stores its PHP-session there.

Configuration

Configuration takes place in the *parameters.yaml* file and accounts for the whole Mapbender instance. Please add the parameter mapbender.cookieconsent with the value true or false. If the parameter is missing or the value is set to false, the banner will not be displayed in your applications.

Example:

```
#Mapbender Cookie Consent Message
mapbender.cookieconsent: true
```

Tip: After changing these parameters you have to clean the contents of the cache-directory (var/cache/ *).

3.6.4 Link



The link element provides a button widget that refers a defined link like a website or script.

Edit element		
✓ Show label		
Title	Mapbender Website	
Tooltip	Visit the Mapbender Website	
lcon	3 Information (inverted)	
Target URL*	https://mapbender.org	
	Save Cancel	

- Show label: Enables or disables text (title) next to the button (default: true).
- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- Tooltip: Text, that will be indicated if the mouse hovers over the button for a longer time.
- Icon: Symbol of the button. Based on a CSS class.
- Target URL Reference to a website or a script.

Hint: It is also possible to deactivate an icon set and/or to use other icons. For more, see *Customizing icons*.

YAML-Definition

This template can be used to insert the element into a YAML application.

```
title:# titleclass:Mapbender\CoreBundle\Element\Buttontooltip:Visit the Mapbender Websiteicon:iconInfoActivelabel:truetrue# false/true to label the button, default is trueclick:https://mapbender.org
```

3.6.5 Coordinates Utility

Coordinates Utility allows two different coordinate operations:

- 1. Zoom to a given point coordinate
- 2. Show the clicked point of the map

Both functions can be accessed with one user interface:

Inees. Institut adente geografie	yyeth 123	14 14 16 17 17a
au 1 der Pflanzen	Coordinates utility	×
Institut &	Coordinate system	
und Geoinformation	WGS 84	~ [
at set 169 Poppelsdorfer Schlass	7.092490 50.725366	Ċ0
Schloss Schloss Zoologisches	Coordinate in map reference system	2
- ageo	789532.38 6572857.16	
Verwaltung der Botanischen	Coordinate search	Center map
Garten Bonn 80 171		Close
Schaugewächshäuser		
asburger ewachshaus	Stein. We see	20 338

Both cases allow a dynamic coordinate transformation. Simply insert and transform coordinates from other systems.

Add element Sidepane - Coordinates utility			
Title	Coordinates utility		
SRS List			
Zoom level*	6		
✓ Add map's srs	list		
	Back Add Cancel		

- Title: Title of the element.
- **SRS List:** You can define additional SRS to which the tool has to transform the coordinates. This list can be left empty.
- Zoom level: Zoom level of the map (default: 6)
- Add map's srs list: If checked, the supported coordinate systems defined in the *Map* will automatically be used by this element and the *SRS Selector* (default: true).

If you define Coordinates Utility as a dialog, you need a *Button* that you place in the Toolbar.

Using the tool

Nees- Institut	Heb Cher 1 2 3	14 14 16
au 1 der Pflanzen	Coordinates utility	×
Institut	Coordinate system	
und Geoinformation	WGS 84	~ 5
at haftlichen at Schloss Schloss	7.092490 50.725366	¢0
Zoologisches	Coordinate in map reference system	2
Institut He ⁸	789532.38 6572857.16	C D 4
Verwaltung der Botanischen Lyrabecken	Coordinate search	Center map
Garten Bonn Bonn 171		Close 3
Schaugewächshäuser		
2 System Pavillion 42	6 0	
assurger, ewachshaus theo	Stein-We and a Ste	38

Get Coordinate

- If Coordinates Utility is opened as a dialog, the map reacts on a click. Click into the map and the click-coordinate is displayed in the dialog.
- Change the coordinate system with the dropdown-list. The click-coordinate is displayed in the given coordinate system.
- The last line therefore shows the click-coordinate in the original coordinate system of the map.
- The button at the end of each text-field allows to copy the coordinate directly into the clipboard.
- If Coordinates Utility is opened via the Sidepane, the button **Coordinate search** will appear that allows switching between a pan-cursor and a coordinate-cursor.

Zoom to coordinate

- The text field can be used to edit your own coordinates. They must be given in the coordinate system that is chosen in the upper dropdown-list.
- With a click on the **Center map** button, the map zooms to the given coordinate and shows the position with an orange symbol.

YAML-Definition

This template can be used to insert the element into a YAML application.

3.6.6 Copyright

The copyright element can be used to show simple text or HTML in a window dialog. It can be opened automatically on application start. It is also possible to integrate links and images into the window (see *HTML*).



Edit element		
🗹 Open automat	ically	
Title	Copyright	
Dialog width	400	
Dialog height	Automatic	
Content*	Mapbender Mapbender is an open source WebGIS solution. Read more at <a <br="" href="https://mapbender.org/">target="_blank">https://mapbender.org	
	Save	

- **Open automatically:** Enable or disable autoopening of the copyright window while starting the application (default: off).
- Title: Title of the element. It will be indicated next to the button.
- Dialog width: Width of the Popup window (default: 300).
- Dialog height: Height of the Popup window (default: 170).
- **Content:** Content of the copyright window, displayed when clicking on the button (or autoopened by starting the application, if enabled).

Refer to a twig file

You can refer to a twig file in the Content area. Please note that the twig file has to contain valid HTML.

Edit element		
Open automat	ically	
Title	News	
Dialog width	500	
Dialog height	Automatic	
Content*	{% include 'WorkshopDemoBundle::news.html.twig' %}	
	Save Cancel	

YAML-Definition

This template can be used to insert the element into a YAML application.

class: Mapbender\CoreBund	le\Element\Copyright	
title: "Copyright"	<pre># Title of the element</pre>	
popupWidth: 300		
popupHeight: 170		
tooltip: "Copyright"	# Text to use as tooltip	
		(continues on next page)

(continued from previous page)

<pre>content: "Lorem ipsum"</pre>	# Edit the text you want to display as copyright text
autoOpen: true	<pre># Automatically open the dialog when you start the application</pre>

3.6.7 Dimensions handler

The dimensions handler can be used to integrate WMS services with a time dimension. WMS-Time services are registered as a normal WMS data source.

WMS-T are inserted almost like WMS in the layersets, with the exception that the time parameter still has to be activated. If it is not activated, the dimensions of the service are ignored and the default value is used when calling the layer in the map.

If a service supports a time dimension, the instance displays the **Dimensions** button. By clicking on this button, the supported time parameters are displayed and time values can be activated by clicking the checkbox. Another click on the form shows more customization options. Here you can optionally further restrict the values from the WMS service as follos to set up the service:

— Dimension	15
time	active
🗌 multiple	
🗌 nearest	
🗌 current	
Name	time
Units	ISO8601
Unit symbol	
Symbol	
Default	2022
Extent	2006/2022/P2Y

- Query type: multiple, nearest, current
- Name: value TIME (name=time)
- Units: format for temporal dimensions (ISO 8601:2000)
- Unit symbol: time unit symbol (service-dependent, e.g. (y) for year)
- **Default**: default time
- Extent (extent slider): Supported extent for the time dimension

After defining the service itself, Dimensions handler supports the following time variables:

- Single time parameter
- List of times
- Time interval

Controlling time parameters

There are two ways to control the time of the WMS. On the one hand, each service with an active time parameter can be controlled via the context menu of the layer in the layertree. In addition, a central slider can be integrated, which can be displayed in any area of the application. The slider can be used to combine several layers with the same extent to control them centrally.

Timeslider in context menu

A timeslider can be integrated via the layertree as an option in the context menu of the layer. To do this, the **Dimension** option must be activated in the *Layertree* element.

Edit element		
Open automat	ically 🕑 Show base sources	
Title	Layer tree	
Menu	Remove layer Opacity Zoom to layer Metadata Dimension	
🗌 Hide info 🕑	Thematic layer	
Themes	conferences 🕑 🖿	
	history 🕑 🖿	
	main 🕑 🗲	
	overview 🕑 🖿	
Allow Reorder at TOC		
	Save Cancel	

After activation in the layertree, a time slider appears in the context menu. To use the feature, the element must first be activated via the checkbox. Then it's possible to alter the timeslider with the cursor.



Timeslider as element

The layers can also be controlled by the dimensions handler element via a central slider. The dimensions handler can be integrated into the sidepane or in toolbar or footer via a *Button*. The configuration of the dimensions handler is done in three steps:

- **Creating the element**: First, the element needs to be created. To do that, integrate the Dimensions handler as new element in the Layouts tab of your Mapbender application.
- **Defining a dimensionsset**: Next, define a dimensionsset. You can create a new set in the element via the "+" button. Type in a title for the set and select a Group.
- **Defining the slider**: At last, you can select the layer instances for the dimensionset that you want to control via the slider. Multiselect is supported, but only instances that have the same extent can be combined with each other. In addition, after the first selection of an instance, a slider appears. There you can restrict the extent for the time display.

When an instance is selected, all instances that do not conform to this default are no longer selectable. Finally, save the configuration to add the Dimensions handler element to the Mapbender application.



Add element Sidepane - Dimensions handler			
Title	Dimensions handler		
Tooltip			
Dimensionsets* +			
Title*	Time		
Group*	34-0-time-interval		
Extent*	2006/2022/P2Y - 2022		
	Back Add Cancel		

- Title: Title of the element
- Tooltip: Labeling of the element on mouseover
- **Dimensionsset**: Group for display of time extent with a title (**Title**), layergroup (**Group**) and time dimension extent (**Extent**)

The following section lists the YAML definitions for the element and the inclusion in the service and leveltree.

If a dimension is specified in the service, it is displayed in the layer metadata.

Dimension: name:'time', units:'ISO8601', unitSymbol:'', default:'2018-01', multipleValues:'', nearestValue:'1',□ ⇔current:'', extent:'2014-01/2018-01/P1M'		
	WMS Dienst mit	Zeitangabe (WMS-T)
	Name:	wms time
	Titel	WMS Dienst mit Zeitangabe (WMS-T)
	Beschreibung:	WMS Dienst mit Zeitangabe (WMS-T) - für Demo- und Testzwecke nutzbar, letzte Änderung im lanuar 2018
	LatLon	EP5G:4326 7.08705. 50.7373. 7.09439. 50.7428
	Grenzen:	
	BoundingBox:	EPSG:4326 50.7373,7.08705,50.7428,7.09439
	2	EPSG:31466 5.62298e+06,2.57677e+06,5.62361e+06,2.5773e+06
		EPSG:31467 5.62415e+06,3.36504e+06,5.62478e+06,3.36557e+06
		EPSG:25832 365018,5.62234e+06,365551,5.62297e+06
		EP5G:25833-58021.7,5.65047e+06,-57438.1,5.65115e+06
	SRS:	EPSG:4326, EPSG:31466, EPSG:31467, EPSG:25832, EPSG:25833
	Punkte nach	Zeit
	Name:	punkte
	Titel:	Punkte nach Zeit
	kaskadiert:	0
	LatLon	EPSG:4326 7.08705, 50.7373, 7.09439, 50.7428
	Grenzen:	
	BoundingBo	x: EPSG:4326 50.7373,7.08705,50.7428,7.09439
		EPSG:31466 5.62298e+06,2.57677e+06,5.62361e+06,2.5773e+06
		EPSG:31467 5.62415e+06,3.36504e+06,5.62478e+06,3.36557e+06
	1	EPSG:25832 365018,5.62234e+06,365551,5.62297e+06
		EPSG:25833-58021.7,5.65047e+06,-57438.1,5.65115e+06
	SRS:	EPSG:4326, EPSG:31466, EPSG:31467, EPSG:25832, EPSG:25833
	Styles:	Name: default
		Titel: default
		Beschreibung:
		Legenden-URL: 75X20 image/png http://wms2016.wheregroup.com/cgi-bin/mapserv?map=/data/umn
		/germany/wms_time.map&version=1.3.0&service=WMS&request=GetLegendGraphic&sld_version=1.1.0&
		layer=punkte&format=image/png&STYLE=default
		Stylesheet-URL:
		Style URL:
	Dimension:	
		name: time', units:1508601', unitsymbol:'', derauit:'2018-01-01 12:00:00', multipleValues:'', nearestValue:'1',
		current: , extent: 2000-01-01/2030-01-01

Element configuration

target: ~ dimensionse title: group:	# ID of the map element ts: Time
dim	ension: # Dimension specification as in the layer configuration origextent: 2014-01/2018-01/P1M active: null type: interval name: time units: ISO8601 unitSymbol: null default: 2017-11 multipleValues: true nearestValue: true current: true extent: 2014-01/2017-11/P1M

Layer configuration

<pre>- name: time units: ISO8601 unitSymbol: null default: 2018-01 multipleValues: false nearestValue: true current: false extent: 2014-01/2018-01/P1M</pre>	<pre>dimension: - name: time units: IS08601 unitSymbol: null default: 2018-01 multipleValues: false nearestValue: true current: false extent: 2014-01/2018-01</pre>	# Dimension specification in layer configuration
--	---	--

Layertree configuration

```
title: Layertree
class: Mapbender\CoreBundle\Element\Layertree
configuration:
   [...]
   menu:
        [...]
        dimension
```

3.6.8 GPS Position

This element provides a button to navigate to your current position and display a symbol at that position. The scale will not be changed until you activate zoom to accuracy (zoom to accuracy on first position).

The element is built upon the Geolocation-API by the W3C. To validate that your browser supports this functionality please take a look at the Can I Use page. The element uses the High Accuracy Parameter that forces the positioning via GPS. If your device is shipped with a GPS-receiver and if it is activated, the positioning is more accurate. Otherwise the WIFI access points are used for positioning.

The midpoint shows the probable position of the device, the outer circle the accuracy of the positioning, that means the region where the position is probably to find.

Compatibility: Internet Explorer and MS Edge deliver without a GPS-reciever at the machine imprecise information. This behaviour is also observable with other applications.



Add element Sidepane - GPS Position			
 Show label Autostart 			
Title	GPS Position		
Tooltip	Display GPS Position		
lcon	♥ Marker ✓		
Average	1		
- Follow			
🕑 Center on first	position		
🗹 Zoom to accur	acy on first position		
	Back Add Cancel		

- **Show label:** Switches the button label on/off (default: on).
- Autostart: Starts element when opening the application (default: off).
- **Title:** Title of the element.
- **Tooltip:** This text will be displayed during hovering over the element with the cursor.
- Icon: Icon to display on button.
- Average: Calculates the average of the last at parameter average defined amount of received GPS coordinates (default: 1).

- **Follow:** Refreshes the map for every received GPS position received, only use with WMS in tiled mode (default: off).
- Center on first position: Centers map only on first received GPS position (default: on).
- **Zoom to accuracy on first position:** Zoom map according to first received gps position accuracy (default: on).

YAML-Definition

This template can be used to insert the element into a YAML application. The element is placed as a button into the toolbar.

class: Mapbender\CoreBundle\Element\GpsPosition			
label: true	# true/false to label button (default: true)		
<pre>autoStart: false</pre>	# true/false (default: false)		
title: GPS-Position	# title of the button		
<pre>tooltip: GPS-Position</pre>	# text to use as tool tip		
<pre>icon: gpsposition</pre>	# icon to display on button		
target: map	# Id of Map element to query		
average: 1	# calculates the average of the last at parameter average defined		
ightarrow amount of received GPS coordinates, default 1			
refreshinterval: 5000	# refresh interval in ms, default is 5000 ms		
follow: true	# default false, true refreshes the map for every received GPS <mark></mark>		
\leftrightarrow position received, only use with W	MS in tiled mode		
<pre>centerOnFirstPosition: true</pre>	# center map only on first received gps position		
<pre>zoomToAccuracy: false</pre>	# zoom map according to received gps position accuracy		
<pre>zoomToAccuracyOnFirstPosition: true</pre>	<pre># zoom map according to first received gps position accuracy</pre>		

3.6.9 HTML

This element allows the integration of HTML anywhere in an application. Figures, links or e.g. texts can be inserted. The following illustration shows the integration of a Mapbender logo in footer, toolbar and sidepane:



The following variables can be integrated in HTML:

- "application" (Entity Application)
- "entity" (Entity HTML-Element)

Configuration

This element has to be integrated in the *Backend*.

Add element Top toolbar - HTML		
Title Content	HTML	
Classes	html-element-inline	
	Back Add Cancel	

- **Title:** Title of the element. The title will be listed in *Layouts*.
- **Content:** Content of the HTML-element. The variables "application" and "entity" are available.
- **Classes:** You can refer to a CSS class for the HTML element. The class can be defined in the css editor.

Configuration examples

Insert picture:

In this example, the Mapbender Logo was integrated in the sidepane. It can be adjusted with a predefined height, background color and transparency as well as a certain padding.

<img src='https://mapbender.org/fileadmin/mapbender/resources/images/logos/Mapbender-Logo.svg'
height='60px' style='background-color:rgb(240, 240, 240, 0.9); padding:10px'>



Insert picture with link:

A linkage was added to the previously inserted logo. It references to the Mapbender website (href='https://mapbender.org') if the logo is clicked on. The link is opened in a new tab because of tar-get='_blank'.

```
<a href='https://mapbender.org' target='_blank'>
<img src='https://mapbender.org/fileadmin/mapbender/resources/images/logos/Mapbender-Logo.svg'
height='60px' style='background-color:rgb(240, 240, 240, 0.9); padding:10px'></a>
```

Variables & HTML-Element

Several variables can be integrated in the HTML-Element.

• Variable: "application.title"

This variable allows the integration of the application title. In the example, this corresponds to "Konfigurationsbeispiele".

The HTML-Code could look like this:

```
<b><span style="font-size:25px;color:#b6dd18;margin-right:50vw"> Anwendung {{ application.title }} </
```

The application title is defined through {{ application.title }}. The term "Anwendung" is an addition and will display independently from the actual title. The style-block defines font size, font width, font color as well as position of the title.

The result for the configuration example looks like this:



• Variable: app.user.username

This variable displays the name of the active user:

Username: {{ app.user.username }}

In this example, the user name is displayed in the toolbar:



• Variable: group.title

The group of a user cannot be defined in a single expression, because Twig only supports the map-filter in higher versions. In order to integrate this variable, a loop will be used:

```
{% for index, group in app.user.groups %}
    Group #{{ index }}: {{ group.title }}
    {% endfor %}
```

In this example, index and group name are displayed in the toolbar:



• Variable: "entity"

The variable { entity } displays the ID and { entity.title }, which displays the title of the HTML-element.

In the following, the variable { entity.title } was integrated with the text addition "HTML-Element". The Styling parameters correspond to those of the example with *application.title*. Text additions, variables and position were simply adjusted for *entity.title*.

```
<b><span style="font-size:25px;color:#b6dd18;margin-right:60vw"> HTML-Element {{ entity.title }} </span></b>
```

These variables could look as follows:



Refer to a twig file

Edit element		
Title	News	
Content	{% include 'WorkshopDemoBundle::news.html.twig' %}	
Classes	html-element-inline	
	Save Cancel	

YAML-Definition

This template can be used to insert the element into a YAML application.

title: 'HTML-Element'	
<pre>class: Mapbender\CoreBundle\Element\HTMLElement</pre>	
<pre>content: Hello, World!Application: {{ application.title trans }} # The variables</pre>	
\leftrightarrow "application" and "entity" are available.	
classes: my-special-css-class	

3.6.10 POI

Generate POI-URLs (aka meeting points) suitable for e-mail. The generated point is projected and displayed in the coordinate system of the map.

	Northard Northard Northard				Contract
titut nvisse urcensi	Share POI 789529.53,6572856.44 @ 1:2500	×	and the second		× set
	Please take a look at this POI:		and a second	15) Poppilizorfix	Poppelsdorfer Schloss
en		li.		Zoole	pischus biut system
		Create link Close			nees wee
2	Participante (1)	der Botanschen Gatten Bonn Bonn 121	Chance of the second se		Botanischer Garten

Add element Map area - POI			
🖌 Use Mailto			
Title	POI		
Body*	Please take a look at this POI:		
GPS	GPS Position 🗸		
	Back Add Cancel		

- Use Mailto: Sends POI by email.
- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Body:** Defines text to display.
- **GPS:** Defines GPS Position in the map.

YAML-Definition

This template can be used to insert the element into a YAML application.

```
target: map# only map-element is possiblebody: 'Please take a look at this POI'# define a text to display
```

3.6.11 Query Builder

The QueryBuilder is not included in the standard scope of Mapbender, but can be added. The Query-Builder provides an element that can be used to display evaluations from the database. You can define SQL queries and give them a title. These are displayed in the applications as tables or in an HTML view and can be downloaded as an Excel list.

For more information visit here: https://github.com/mapbender/query-builder/blob/master/README. md

Queryguilder Demo iiie rike Report 1: Time and Date iiii @ @ @ rike rike rike rike rike rike rike rike rike rike rike rike rike rike rike <			_	
Itile Title Report 1: Time and Date Imediation and the state of of the state	QueryBuild	ier Demo		And
Title ● Report 1: Time and Date ● ■ ■ © © © Hello world ● ■ © © © Report 3: Mapbender users ● ■ © © © Report 2: Mapbender users ● ■ © © © Report 2: Mapbender users ● ■ © © © Results: Report 3: Mapbender users ● ■ © © Image: Report 3: Mapbender users ● ■ © © © Image: Report 3: Mapbender users ● ■ © © © Image: Report 3: Mapbender users ● ■ © © © © © © © © © © © © ©	+	search		Eschmar SEGBURG Menden Steaman Steaman
Report 1: Time and Date Image: Conditient of Conditi	Title	\$		
Hello world Image: Coordinate rusers Report 3: Mapbender users Report 2: Mapbender users Report 3: Mapbender users Results: Report 3: Mapbender users Image: Results: Report 3: Mapbender users Im	Report 1: Time a	nd Date	1 II	sort
Report 3: Mapbender users Report 2: Mapbender applications Image: Conditionation of the second of	Hello world		1 II	Mondorf Berghem
Report 2: Mapbender applications Results: Report 3: Mapbender users Id	Report 3: Mapbe	nder users	∠ ⊞ C C û	Or Nederple's
Results: Report 3: Mapbender users Image: margin discontrational dis	Report 2: Mapbe	nder applications	1 = C C û	
Results: Report 3: Mapbender users in				
Id Ip Id root Id AMustermann Id BMustermann Id CMustermann Id CMustermann Id DMustermann Id BMustermann Id BMustermann <th></th> <th>Results: Report 3:</th> <th>Mapbender users</th> <th>×</th>		Results: Report 3:	Mapbender users	×
1 root 2 A Mustermann 3 B Mustermann 4 C Mustermann 5 D Mustermann 6 E Mustermann 6 E Mustermann 6 F Mustermann Charter B F Mustermann Sketches F Mustermann Coordinate secure F Mustermann		id	17	username 🔶 🎉
2 A Mustermann 3 B Mustermann 4 C Mustermann 5 D Mustermann 6 E Mustermann 6 E Mustermann 1 P Mustermann 6 F Mustermann 2 Cordinate Export HTML-Export Cancel		1		root Rauscher Ch
3 B Mustermann 4 C Mustermann 5 D Mustermann 6 E Mustermann 6 E Mustermann 1 P Mustermann 2 P Mustermann 2 P Mustermann 1 P Mustermann 2 P Mustermann 2 P Mustermann 2 P Mustermann Sketches Export HTML-Export Cancel		2		A Mustermann
4 C Mustermann 5 D Mustermann 6 E Mustermann 1 F Mustermann 1 P Mustermann 1 P Mustermann 1 F Mustermannn 1 <		3		B Mustermann
5 D Mustermann 6 E Mustermann Layer tree 7 7 P Mustermann Line/Area * Sketches Export HTMLExport Cancel		4		C Mustermann Scale 1: 99K to Oeinghoven
6 E Mustermann Layer tree 7 1 F Mustermann Line/Area * Sketches Export HTML-Export Cancel		5		D Mustermann
Layer tree 7 FMustermann Line/Area * * Sketches Export HTML-Export Coordinate-setures Interesting		6		E Mustermann
Line/Area Sketches Export HTML-Export Cancel	Layer tree	7		FMustermann
Sketches Export HTML-Export Cancel	Line/Area	•		
Coordinates arms	Sketches			Export HTML-Export Cancel
Data Upload Bonn View manager Bonn	Coordinate Data Uploa View mana	ad ger		Regelerationality

3.6.12 WMS Loader

Opens a dialog in which a WMS can be loaded via the getCapabilities request. It is possible to load WMS 1.1.1 and WMS 1.3.0.

WMS loader		×
Example: https://wms.w VERSION=1.3.0&REQUE	/heregroup.com/cgi-bin/mapbender_user.xml? ST=GetCapabilities&SERVICE=WMS	
Service URL:*	https://wms.wheregroup.com/cgi-bin/mapb	
User:		
Password:		

Edit element				
Open automatically Split layers				
Title	WMS loader			
Default format*	image/png ~			
Default info	text/html ~			
	Save Cancel			

- **Open automatically:** Opens the element when application is started (default: false).
- **Split layers:** Splits layer on load of the service (default: false).
- **Title:** Title of the element. The title will be listed in *Layouts* and allows to distinguish between different buttons. It will be indicated if "Show label" is activated.
- **Default format:** image/png, image/gif, image/jpeg (default: image/png).
- Default info format: text/html, text/xml, text/plain (default: text/html).

You need a *Button* to show this element.

How to add a WMS by defining a link

You can add a WMS to Mapbender by defining a link, e. g. in your *FeatureInfo* or your search results. The link has to look like this:

```
mb-action="source.add.wms"
                                    # defines action to add a WMS
mb-wms-merge="1"
                                    # adds the WMS only once, if WMS is already part of the application
\rightarrow it will use the WMS which is there (default: 1)
mb-layer-merge="1"
                                    # activate the layers passed mb-wms-layers and do not disable the
\rightarrow layers which are already active (default: 1)
mb-wms-layers="Gewaesser,Fluesse" # defines the layers to be activated, _all activates all layers, D
→ default all layers are deactivated
href oder mb-url
                                    # refer to the WMS getcapabilities URL
mb-add-vendor-specific="bplan=123" # define a vendor specific that will be added to the requests
\rightarrow (version 3.2.9 and up)
mb-infoformat="text/plain"
                                    # defines the GetFeatureInfo format for the WMS (default: text/html)
```

YAML-Definition

This template can be used to insert the element into a YAML application.

target: ~	# Id of Map element to query
tooltip: 'WMS Loader'	# text to use as tooltip
<pre>autoOpen: false</pre>	<pre># true/false open when application is started (default: false)</pre>
<pre>defaultFormat: 'image/png'</pre>	<pre># image/png, image/gif, image/jpeg (default: image/png)</pre>
<pre>defaultInfoFormat: 'text/html'</pre>	<pre># text/html, text/xml, text/plain (default: text/html)</pre>
<pre>splitLayers: false</pre>	<pre># split layer on load of the service (default: false)</pre>
CHAPTER

FOUR

BACKEND

The backend is the administration interface of Mapbender: It allows the management of applications and data sources as well as securing them through users and groups. To install and set up Mapbender, please visit the *Installation* pages or the *Quickstart*. In its local standard configuration, the backend can be accessed via http://localhost/mapbender. After a successful login with the root user, the following pages are available:

4.1 Applications

4.1.1 Base data

Base data determines the fundamental information and settings of an application. They can be configured through a mask in the application settings in the *Backend*. You can find more details on application creation under *Quickstart*.

Settings

- **Title**: The application's name.
- URL Title: How the application is shown in the URL field. No special characters allowed.
- **Thumbnail**: Uploadable image file from the file directory that will be displayed in the application overview. Click on **Select File**.
- **Description**: Text input field that can store the application's description, if provided.
- **Persistent map state**: Stores the state of specific map parameters and settings across sessions. For more information, please see *Share Elements*.
- Show Splashscreen: Shows a splashscreen on application startup to indicate the loading time.

Mapbender Demo		
Base data Layouts Layersets CSS Security		Uiew
Title*		
Mapbender Demo		
URL Title*	XXX	
mapbender_demo	0.0	
Thumbnail	and the second second	
Durchsuchen Keine Datei ausgewählt.		
Description		
Mapbender demo application showing many elements in action		
Persistent map state Show Splashscreen		
		Save Cancel

Configuring the Splashscreen

The splashscreen enhances your application's appearance by displaying an image logo alongside the application's title. To configure the splashscreen image, follow the steps below:

- 1. Open the parameters.yaml file located in your Mapbender installation. For more on the file itself, see YAML Configuration (Configuration and Application files).
- 2. Create or look for the key branding.splashscreen_image.
- 3. Define the splashscreen image using one of the following methods:
 - **File Path**: Specify a single file path relative to the *application/public* directory in your Mapbender installation.

```
parameters:
    branding.splashscreen_image: path/relative/to/public/myimage.png
```

• Array: Utilize an array format where keys correspond to the application's slug. This allows you to customize the splashscreen image for each application. Use the key default to provide a fallback image for applications not explicitly defined.

```
parameters:
    branding.splashscreen_image:
    sample_application: path/relative/to/public/sample_application.png
    another_application: path/relative/to/public/another_application.png
    default: path/relative/to/public/myimage.png
```

If the splashscreen image is not configured, the logo (branding.logo) will be used for all applications.

Moreover, the appearance of the splashscreen is customizable via CSS variables. Please switch to *CSS editor* for an example.

4.1.2 Layouts

The Layouts section in the *Backend* of an application gives an overview of the regions (layout sections) of the application. In those regions, the elements of the application are listed. An overview of all elements is available under *Elements*.

Note: Different templates can have different regions: In the demo applications you can see two different region layouts. Not every element can be used in every region. Mapbender cares about that.

Layout of the Fullscreen template:

- Top toolbar (region for Buttons, Links, HTML,...)
- Sidepane (region for Layertree, Legend, Search, Print, HTML,...)
- Map area (region for Map, Scalebar,...)
- Footer (region for Copyright, Activity Indicator, Scale select,...)

Layout of the Mobile template:

- Footer (region for Copyright, Activity Indicator, Scale select,...)
- Map area (region for Map, Scalebar,...)
- MobilePane (region for dialogs like Layertree, Legend, BaseSourceSwicther, FeatureInfo,...)

+

The button located at the top right of each region allows adding elements. After pressing the button, a dialog will open, which allows for the selection of an element and its subsequent configuration.

All elements in an application can be moved between regions using drag and drop.

The regions themselves can be configured using the option for region Map area and MobilePane.



button at right. There is no configuration

The regions Top toolbar and Footer provide the following configuration options:

Configuration of the Top toolbar and the Footer

The Top toolbar and the Footer provide the following configuration options:

- **Screen type** (Any, Mobile, Desktop. Default: Any): The region will not be displayed when other screen types are used. *Any* will always show the region.
- Alignment (Left, Right, Center. Default: Right): Sets the alignment for the buttons, texts, links.
- Generate menu for buttons:Creates a dropdown menu for the elements.
- Menu label input field: Labeling for the dropdown menu.

Tip: Note: Using the dropdown menu is especially handy on mobile devices. There is a code snippet in *CSS editor* that adds a scroll bar to the menu and helps to increase the user experience.

YAML Configuration

This template can be used to configure the **properties** of the toolbar in a YAML application:

```
- name: toolbar
properties:
    item_alignment: right # right/left/center
    screenType: all # desktop/mobile/all
    generate_button_menu: false # true/false
    menu_label: "Menu" # NULL or text
```

Besides, this template can be used to configure the **properties** of the footer in a YAML application:

name: footer	
properties:	
item_alignment	: right # right/left/center
<pre>screenType: al</pre>	l # all/desktop/mobile
generate_butto	n_menu: false # true/false
<pre>menu_label: "M</pre>	enu" <i># NULL or text</i>

Configuration of the Sidepane

The Sidepane provide the following confi	guration options through th	eir 🌣	button:
Sidepane			
Titel	Тур	Тур	Akkordeon
	·) F		

					_	
Ebenenbaum	Ebenenbaum	Bildschirmtyp	Alle	~	P 前	1
Skizzen	Skizzen	Breite	645nx		P 前	[
Legende	Legende		lankan		Ð 🗊	[
Koordinaten Utility	Koordinaten Utility	Größe veränderbar		0	P 前	[
About Mapbender	HTML	Position	Rechts	~	P 前	[
Suchen	Suchen	Geschlossen :	starten		Þ 前	[
Ansichtsverwaltung	Ansichtsverwaltung				Þ 🗊	

- **Type** (Accordion, Buttons, Unstyled. Default: Accordion): See explanation below.
- Screen type (Any, Mobile, Desktop. Default Any): The region will not be displayed when other screen types are used. Any will always show the region.
- Width (in px) (in px. Default: 350px): Width of the Sidepane in Pixels.
- **Resizable** (Default: true): Allows to resize the width of the sidepane.
- **Position** (Left, Right. Default: Left): Defines the placement of the sidepane.
- Initially closed (Default: disabled): Defines whether the Sidepane should be closed or open on start of the application.

The option **Type** adjusts the inserted elements:

- Accordion shows elements via tabs.
- Buttons shows elements via buttons.

\$

• Unstyled does not contain any styling options at all and displays the elements in the configured *Backend* order.

The option **Resizable** uses a minimum size of 120 px and a maximum of 95 % of the screen's width. These values can be further restricted by using custom css:

```
.sidePane.resizable {
    min-width: 200px;
    max-width: 500px;
}
```

YAML Configuration

This template can be used to configure the **properties** of the sidepane in a YAML application:

```
- name: sidepane
properties:
    name: accordion # tabs (for button) / accordion / NULL (for unstyled)
    align: right # right/left
    closed: false # true/false
    screenType: all # all/desktop/mobile
    width: "654px"
```

Button area (Elements)

Every element offers a set of buttons for configuration. The button area helps configuring elements in their specific regions. The following button functions are available:



- **Toggle show/hide element**: A shown element is visible in the application. A hidden one is not visible in the application itself, but can still be adjusted in the *Backend*.
- Show on mobile screens: Displays an element only on mobile-sized screens.
- Show on Desktop screens: Displays an element only on Desktop-sized screens.
- Edit: Adjusts an element.
- Restrict element access: Sets specific visibility permissions for an element.
- **Delete**: Removes an element from both front- and *Backend*.

Edit

The button opens a configuration mask for a specific element. The *Elements* overview page can help you to look up a setting for a specific element.

Restrict element access

The button opens a **Secure element** window that allows the configuration of the *View* right for users/groups.

Without configuration, an element has no access restriction and is available to the users/groups that can access the application.

When **View** access rights are set, only the defined users/groups get access to the element.

Add users to restrict access to them with the provides the necessary rights.	+	button. A set checkmark next to the user account
Restrict element access		-
	+	
Filter View		
La Bob View	Û	

```
Save Cancel
```

After setting specific access rights, the security key turns red.

Top toolbar		\$
Title	Туре	+
Base source switcher	Base source switcher	0 🛛 🖵 🌣 🔑 🗊
FeatureInfo	Button	0 🗋 🖵 🌣 🔑 🗊
Legend	Button	◎ 🛛 🖵 🌣 🔑 🗊
WMS loader	Button	◎ 🛛 🖵 ‡ 🔑 🗊

You can find more security details under *Permission management*.

Delete

Removes an element from both front- and *Backend*.

4.1.3 Layerset

Layersets are logical containers that can contain one or more layerset-instances (WMS services). In the demo applications two layersets are defined: Layerset "main" for the main map and layerset "overview" for the overview map. The names of the layersets can be freely chosen. Moreover, more than one layerset can be chosen in the map element. Layertree shows the layerset name when thematic layers is activated.

Layerset Overview Page

This page shows all layersets of an application. Every layerset is displayed as a container that holds services. On the page, there are buttons that help to manage the layersets:

Layerset actions



Instance actions

	0	: Toggle show/	hide instance			
•	۵	: Edit instance				
• Manhender		: Delete instan	ce			& Annemeldet als: mot
mappender	Ainvendungen L	secondenies second second				Augunetaet au. root -
			Demo		📮 Anzeigen	
			Filtern		+	
			main		+ 0 8 8	
			Id Titel	Datenquelle	Тур	
			410 Mapbender Users	#41 Mapbender Users	± WMS @ @ ⊕	
			411 OSM Demo	#61 OSM Demo	±wms ∞ ¢ 🖯	
			overview		+ 0 🗹 🖹	
			id Titel	Datenquelle	Тур	
			412 OSM Demo	#61 OSM Demo	↓ WMS @ 0 ≘	
					Speichern Abbrechen	

Layerset-instances

Layerset-instances contain options to configure certain WMS parameters: image-format, info-format, exception-format, scales for the different layers etc. Layerset-instances can be configured by clicking on the gear symbol.

🕹 Mapbender	Applications - Sources - Security										& Logged in as: root
	OSM Demo WMS instance Z/28 (Bound instance)						•	ionvert I	S to share	ource 🖵 d instance	
	Origin URL: https://osm-demo.where	group.com/service						Sav	e 84	ack	
	Title *			Dimensions						+	
	OSM Demo										
	Opacity			Vendor specific						+	
	100		*	BaseSource							
	Format *			Proxy							
	image/png		*	 Transparency 							
	Infoformat			✓ Tiled							
	text/html		*	Layer ordering *							
	Exceptionformat			standard						~	
			*								
	Tile buffer										
	0		40								
	BBOX factor										
	1.25										
	Title	Minsc		Maxsc	active	select	info	to	ggle		
						allow on	allow	n allo	w on		
					¥			8 9		_	
	OSM Demo				Y			9		-	
	 OSM Demo WhereGroup 				Y	2 2				-	
								Sav	e B	əck	
			Mapbe	nder 3.2.4							

As soon a WMS service is integrated in a layerset, it is linked as a layerset-instance within the application.

The screenshot above shows the *bound instance* 2/28 based on a WMS service. The associated data source is number 2, the layer's instance itself has the number 28. It is based on the WhereGroup OSM service and can be configured for the application in this dialog.

The properties of the WMS-Capabilities:

- **Title:** Title of the instance that is shown in the layerset list and their instances.
- **Format:** The image format which is used to get the map images for the application via the GetMap request. For raster data and aerial imagery the JPG format is recommended, in case of street maps the PNG format should be preferred. If you are in doubt use PNG.
- **Infoformat:** The format which is used for the GetFeatureInfo requests to the WMS. If you are in doubt use text/html or an analog HTML format that can be used in the dialog of the *FeatureInfo* element. Another possibility is text/plain.

• Exceptionformat: The format for error-messages that are returned by the WMS service.

The properties for the application

- **Opacity:** Choose the Opacity in percent. This value can be changed by the user in the *Layertree*, if it's made available in the corresponding menu.
- **Tile buffer:** This parameter applies to services that are tiled and specifies whether to retrieve more surrounding tiles. With that they are already downloaded and visible during a pan movement. The higher the value, the more surrounding tiles are retrieved. Default: 0.
- **BBOX-Factor:** This parameter applies to services that are not tiled. You can specify how big the returned image should be. A value greater than 1 will request a larger map image. Default: 1.25 and you are free to set it to 1.
- Vendor Specific Parameters: See below.
- Visible: The service can be set visible with this option.
- **BaseSource:** The service should be treated as a BaseSource. This affects the *BaseSourceSwitcher*, which should only display BaseSources, and the *Layertree*, where these BaseSources can be hidden. See also the *hints* below.
- **Proxy:** If activated, the service will be requested via a proxy in Mapbender. See the *hints* below.
- **Transparency:** If this switch is enabled (that is the default), the service is requested with a transparent background. So in the WMS GetMap request with the parameter TRANSPARENT=TRUE.
- Tiled: The service is requested in tiles. The standard is not tiled. See the following *hints*.

Layer-Order:

There are two ways to pass a layer order to the layer tree:

- Standard
- QGIS Style

This distinction has its origins in the way WMS services and capabilities documents are built.

The OGC e-learning module for Web Map Services describes the structure of an example WMS.

This WMS displays some point, line and polygon objects and raster images. The Capabilities document lists images (e.g. DTM) more at the top of the document than points (e.g. osm_points as the penultimate layer). Mapbender takes this approach both in the DataSources, where the service is loaded and registered in Mapbender, as well as in the Layerset instances.

In the layer tree, however, this order revolves. That is because, from our experience, users are accustomed to find layers that are higher up in the layer-tree also displayed as top layers. This configuration is also commonly found in a desktop GIS. Furthermore, points are displayed in the layer-tree above raster data.

The QGIS Server behaves differently here. A WMS can be easily deployed to a QGIS server using the QGIS project file. Order of the layers in the WMS Capabilities is then the same as the order used in your own QGIS project. So in general: points above, further below the lines, then finally the polygon data or raster images. QGIS and QGIS servers are not the only programs that can do this. But they are the best. However, this information is irrelevant for the GetMap call, because the order of the requests and how they are delivered to the server and back is solved in the WMS specification.

The following table summarizes the behavior again:

	layer order standard	layer order QGIS style
WMS Capabilities (from top to bottom)	polygon, line, point	point, line, polygon
Layerset-Instance (from top to bottom)	polygon, line, point	point, line, polygon
Layertree (from top to bottom)	point, line, polygon	point, line, polygon

This allows Mapbender to respond in the different ways that a WMS Capabilities document can be built up by simply adjusting the order in the layer tree.

Shared and bound instances

By default, all layerset-instances are created as bound instances. Bound instances must be configured individually for each application. Shared instances allow the use of a configured layerset-instance across multiple applications. Therefore, if multiple applications share the same configuration of a layersetinstance, the use of a shared instance saves the time of manually configuring the layerset-instance for each application. Changes made to a shared instance take effect in all applications using said instance.

A bound instance can be transformed into a shared instance by clicking on the blue button labeled **Convert to shared instance**. To transform a shared instance back into a bound instance the same button, now labeled **Convert to private instance**, can be used.

OSM Demo			Source 🖵
WMS instance 2/27 (Bound instance)			Convert to shared instance
Origin URL: https://osm-demo.wheregroup.com/service			Save Back
Title *		Dimensions	+
OSM Demo			
Opacity		Vendor specific	+
100	~	-A RaceSource	
Format *			

Shared instances are marked with a Wi-Fi symbol in the "type" column of the layerset overview.

OSM Demo			Source 🖵
WMS instance 2/27 (Shared instance)			Convert to bound instance
Origin URL: https://osm-demo.wheregroup.com/service			Save Back
Title *		Dimensions	+
OSM Demo			
Opacity		Vendor specific	+
100	~	RaceSource	
Format *		Proxv	

Bound instances are marked with an anchor symbol in the "type" column of the layerset overview.

ld	Title	Туре	+	¢ ×
1/22	Mapbender Users (Mapbender Users)	🕹 WMS	۲	¢ ×
2/25	OSM Demo (OSM Demo)	🗢 WMS	۲	¢ ×

Shared instances will appear as sepatrate data sources. To incorporate a shared instance into an application simply add a data source to the application and select the shared instance from the list.

Select source	
Filter	
WMS#2: OSM Demo	Shared instance #25
WMS#1: Mapbender Users	
WMS#2: OSM Demo	
	Cancel

All shared instances can be viewed under **Sources** -> **Shared instances**.

Layer Configuration

The layer table offers several checkboxes and two scale visibility fields that adjust the functionality of your Service Instance. Please note that the checkbox on top changes all the layer instances for the respective configuration at once.

	Title	Minsc	Maxsc	active	select		info		toggle		
					allow	on	allow	on	allow	on	
				4				•			
5	Mapbender Users			V		•			•		
•	User			•		•					
٠	Name			•		•	4	1			

- Title: Layer title from Service information shown in Mapbender, adjustable.
- **Minscale / maxscale**: the scale range in which the layer should be displayed, 0 or no entry = no scale limitation.
- Active (on/off): Enables/disables a layer for the individual application layer. If not set, all other checkboxes of the same layer will be ignored.
- Select allow: Layer is active when the application starts.
- Select on: Selectable in geodata explorer.
- Info allow: layer info is active when the application starts.
- Info on: Layer provides feature info requests, info default activates the feature info functionality.
- **Toggle allow**: Folder can be opened via Layertree.
- **Toggle on**: Opens the folder on start of the application.

Back

- **Reorder**: Allows to reorder the layers with drag & drop while using the application.
- ... -> Opens a dialog with more information:
- Layer's name: Layer name of the service information (for getMap-Requests, not adjustable).
- **Style**: If a WMS provides more than one style, you can choose a different style than the default style.

Notes on the effects of each configuration

Basesources

There are many ways to fill the Layertree and work with basic services:

- e.g. by hiding them in the layer tree and using the *BaseSourceSwitcher*.
- or by work with the possibilities of the *thematic layer tree*. This option will show the layerset name with a folder and checkbox in the layertree. You can define whether the layerset's folder should be shown and whether it should be opened on start.

Which option you choose depends entirely on your preferences.

Ргоху

The use of a proxy makes sense if you want to avoid that the web browser accesses the service as a client directly, which is the default for OpenLayers-based applications. If this switch is activated, Mapbender accesses the services from its own URL, processes the images and displays them on the map. With that it is easy to provide a network-protected service secured by firewalls that can only be accessed by the web server on which Mapbender is running.

Tiling, map-size and performance

The "Tiled" parameter is used to request the map image in individual tiles rather than as a whole image. This should be turned on in general, if you use Mapproxy to provide a tiled service. But it also makes sense for normal, un-tiled services, since the perceived waiting time for the user gets lower: The map image appears, although not all tiles have been retrieved yet.

Keep in mind that the number of requests to a WMS increases rapidly: Depending on the screen resolution and the set tile size in the *Map*, many requests are sent to the server. Although the returned images are not very large (usually you set tile sizes of 256x256 or 512x512 pixels), they are large in numbers. This is also valid in regard to the **tile buffer**. So it is a trade-off and a case-by-case distinction how to address the service. The performance can also be increased by setting the scales of a layer in the layerset-instance.

There are also some WMS services that only support a maximum image size that cannot be used with the high resolutions request that Mapbender can call. The Fullscreen template can be sized to the maximum screen width and the requested map image is then approximately the width and height of the visible browser window.

Vendor Specific Parameter

In a service instance, vendor specific parameters are appended to the WMS request. In Mapbender, the vendor specific parameters can be used to append user and group information of the logged-in user to the WMS request. Fixed values can also be transmitted. The following example shows the definition of a parameter "group", which passes on the group of the user currently logged into Mapbender.

Vendor specific	c		-
+			
Vstype	user	∨ ×	
Name	groupIds		
Default	\$groups\$		
🗌 Hidden			

- Name: Parameter name in WMS request.
- Default: Default value.
- Vstype: Mapbender specific variables: group, user (users), simple.
- Hidden: If this value is set, the requests are sent on the server so that the parameters are not directly visible.

The item is useful for passing the service on only to specific users and groups. This happens e.g. for users via the \$id\$ and for groups via the parameter \$groups\$.

Further information

- You can find information about using layersets under Quickstart chapter 4. Configure Sources.
- Further tips on manipulating WMS can be found under *Performance*.
- The relevance of layersets for the display in the layertree is described under *Workflow thematic Layertree*.
- Disabling one or more layersets for an application is possible in its Map settings.
- Likewise, individual thematic layersets can be (de)activated via checkbox in the layerset configuration so that they are (not) visible in the map on application startup.

4.1.4 CSS editor

Mapbender offers an CSS editor for every application which easily allows you to change its style (colors, sizes, icons, ...). It is possible to define additional CSS classes that will overwrite the default style. You can use scss in the editor. And you can refer to an scss-file in your bundle.

Demo								
Base data	Layouts	Layersets	css	Security				View
							Save	Cancel

Tip: A browser inspect tool can help you to find out the CSS classes you want to change.

Examples

Add scrollbar to the top toolbar

When you use the menu option in the top toolbar you can define at what size of the screen the height should be reduced and a scrollbar should appear. This enhances the usability of the application on mobile devices.

```
// Scrollbar in Toolbox
.dropdown-menu {
   overflow-y: auto;
   max-height: calc(100vh - 100px);
}
```

The function itself can be found in the *Layouts* tab: Click the gear button and activate the checkbox Generate menu for buttons.

Adjust the splashscreen

If your Mapbender application has its splashscreen active via *Base data*, it is possible to customize it further via CSS:

:root {	
primary: #079ee0;	/* application-wide primary color, will be used \square
\hookrightarrow as the loading indicator's color */	
splashscreen-border: none;	/* border around the splashscreen dialog, \square
→generate using e.g. https://html-css-js.com/css/gener	rator/border-outline/ */
splashscreen-border-radius: 25px;	/* determines the radius of rounded corners
\hookrightarrow around the dialog */	
splashscreen-background: rgba(255,255,255,0.8);	<pre>/* background color of the splashscreen */</pre>
splashscreen-fade-out-duration: 200ms;	<pre>/* animation duration of the fade out */</pre>
3	

4.1.5 Security (Application tab)

Each application has its own security tab. There, you can set individual permissions for a single application or its elements.

Note: A set global permission overwrites an individual permission set on this page.

Assign an Application to a User/Group

Per default, all applications are available to all *Users* and *Groups and Roles* that have specific permissions to the *Backend*. Nethertheless, it is possible to hide applications from individual accounts:



- 1. Edit your application by clicking
- 2. Choose the **Security** tab.
- 3. Publish your application for everyone by clicking Security [] public access or in the application

overview by clicking Toggle public access



- 4. For an individual configuration, click the **Add users and groups** button and configure your selection. Then, set permissions like view, edit or delete the permission table.
- 5. Logout from Mapbender and log in again with a configured account to test the configuration.
- 6. Another method would be to choose **Security** [] **Global Permissions** [] **Applications** to quickly set global application rights for several users or groups.

🕹 Mapbender	Applications Sources Se	curity					Logged	in as: root 🔻
Ba	asic Demo							
Bas	e data Layouts	Layersets CSS	Security				Uview	
	Filter							
			View 🔮	Edit 🕑	Delete	Permission Management 💿		
	L Mallory		View	Edit	Delete	Permission Management	Û	
	L Bob		View	Edit	Delete	Permission Management	Û	
	L Alice		View	Edit	Delete	Permission Management	Û	
	L root		View	Edit	Delete	Permission Management	Û	
							Save Cancel	

Assign single elements to a User/Group

Per default, all elements of an application are available to all *Users* and *Groups and Roles* that have permission to it. It is possible to hide single elements from individual accounts:

- 1. Edit your application by clicking
- 2. Choose the Layouts tab.
- 3. Every element has a *Restrict element access* button. Use it for the element that should be only availale for selected users/groups.
- 4. Now, add the users/groups via the **Add users and groups** button. Then, set permissions like view, edit or delete via the rights table.
- 5. Test your configuration. For example, open the application with a user account that has (no) rights to a previously configured element.

Top toolbar		\$
Title	Туре	+
Base source switcher	Base source switcher	⊘ □ □ ↓ ≯ ₽ 前
FeatureInfo	Button	④ □ 모 \$\$ ₽ û
Legend	Button	④ □ □ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$ \$\$
WMS loader	Button	⊘ [] 🖵 ‡ 🔑 û

4.2 Sources

With Sources, you can register OGC WMS and OGC WMTS/TMS services in version 1.1.1 and 1.3.0 in Mapbender.

Further information about the registration process of services and their usage in applications is available in the Quickstart chapter *Load sources*.

4.2.1 Load sources

Tip: It is important to check the service before it is registered in Mapbender. To do that, open the getCapabilities-Request (see example in Service URL) in your browser.

To register a service, click on **Add source**:

- Type: Mandatory service type selection (OGC WMS or OGC WMTS / TMS).
- Service URL: URL to the Capabilities document of the service (e.g. OGC WMS Version 1.3.0:)
- **Username / Password**: Input of the username and the password for secured services.

Click on Load to register the service to the repository.

Add source	
Type *	
OGC WMS	~
Service URL *	
$http://osm-demo.where group.com/service? {\sf SERVICE=WMS} \\ {\sf WMS} \\ {\sf Version=1.3.0} \\ {\sf REQUEST=GetCapabilities} \\ {\sf Version=1.3.0} \\ {\sf Version=1.3.0} \\ {\sf REQUEST=GetCapabilities} \\ {\sf Version=1.3.0} \\ {\sf Requested in the term in ter$	
Username	
Password	
	Load Cancel

After a successful registration, Mapbender will provide an overview of the service.

4.2.2 Sources Overview

The sources and shared instances sections list and provide additional information about the services registered:

- Filter: Search for services names, URLs, types and descriptions.
- **Show metadata**: Shows metadata about a specific service. Opens a new field that lists specific metadata, Mapbender applications that use the source, contact information, details (e.g. service version) and layers.
- **Update source**: Updates service information by reloading the getCapabilities document.
- Delete source: Removes the registered service from Mapbender.

Sources	
Sources Shared instances	
+ Add source	FilterQ
Mapbender User ^{#25}	
Type: WMS 1.3.0 URL: https://wms.wheregroup.com/cgi-bin/mapbender_user.xml?VERSION=1.3.0 Abstract: Mapbender User Reference	
OpenStreetMap (OSM) Demo WhereGroup ^{#19}	
Type: WMS 1.3.0 URL: https://osm-demo.wheregroup.com/service?VERSION=1.3.0	
Abstract: This is an OpenStreetMap Demo Service of WhereGroup	

4.2.3 Sources menu button

In the metadata dialog of a specific service, it is also possible to click on the menu button (top right) that allows:

- Update source: Updates service information by reloading the getCapabilities document.
- **Create shared instance**: Creates a new shared instance from the specific service. The instance is listed in the Shared instances tab.
- **Delete**: Removes the registered shared instance from Mapbender.

WMS Ope	nStreetMap (OSM) Demo WhereGroup	=
	₽ Update source	
		🗢 Create shared instance
Motadata Applic	ations Contact Datails Lawers	🗇 Delete
Mecadaca Applic	ations contact Details Layers	
Title:	OpenStreetMap (OSM) Demo WhereGroup	
Version:	1.3.0	
Origin URL:	https://osm-demo.wheregroup.com/service?VERSION=1.3.0	
Abstract:	This is an OpenStreetMap Demo Service of WhereGroup	
Online Resource:	https://osm-demo.wheregroup.com/service	
Exception Formats:	XML, INIMAGE, BLANK	
Fees:	None	
Access Constraints:	This service is intended for private and evaluation use only. The geodata is licensed as Open Data Commons Open Datal	base Lizenz (ODbL)
	(http://opendatacommons.org/licenses/odbl/)	. ,

4.2.4 Updating sources

To update a source in the *Backend*, you first need to navigate to the Sources *Backend* list. On this page, look for the layer you wish to update via scrolling or use the search box. After you've found it, click on its

Refresh button. You can then update the WMS: If you wish, modify the URL or other settings, such as user name and/or password.

Hint: Of course, it is possible to update a source without changing any parameters. The Capabilities document is loaded again.

Moreover, there are two checkboxes handling layer updates:

Jpdate source (OGC WMS)	
Service URL *	
https://osm-demo.wheregroup.com/service?VERSION=1.3.0	
Username	
Password	
✓ Activate newly added layers	
✓ Select newly added layers	
Load Cancel	

• Activate newly added layers: If active, the newly added layers will automatically set active in embedded applications. If the checkbox is not checked, new layers will not appear in the layertree. • Select newly added layers: If active, the newly added layers will automatically be visible and set active in embedded applications. However, Activate newly added layers must also be set for this. If Select newly added layers is not set, the layer will appear in the layertree but will not be activated.

If you want to save the changes, click the Load button to refresh the WMS. This will re-read the getCapabilities document. The updated version will be displayed in the configuration settings, with changes applied in applications using the service.

4.3 Security

The security for domain objects is implemented in Mapbender using a permission system. It allows global authorizations for areas and individual authorizations for objects. Therefore, it provides flexible permissions and security for the following entities:

4.3.1 Users

User are implemented as FOM\UserBundle\Entity\User and stored in the database. The entity has only some basic information about the user itself, more complex user data will have to be implemented by user profiles (yet to be done).

The bundle provides all means to administrate users by admin as well as self-registration and password recovery.

The user with the id 1 (root) is special, as this user is created during installation and will always be given full access. If all is lost, you can use this user to manage everything. And in the event that the credentials for this user are also lost, a *console command* (fom:user:resetroot) is available for resetting.

Forgot Password

If a user has forgotten his/her password, he can use the "Forgot password?" link in the Login screen to request a new one. For that he types in his username or email address.



Forgot password

To reset your password please provide your username or your e-mail address.

User name or Email *

Back to login

Require password

After that, the user should receive an email with a link which leads to a page where a password reset is possible. The link is not valid anymore after this operation. The text of the mail can be customized in the */FOM/UserBundle/Resources/translations/messages.en.xlf* file.

The functionality can be switched off in the *doctrine.yaml*.

```
fom_user:
    reset_password: true # true/false
```

Registration

Users can self-register themselves in Mapbender. For this, you have to adjust the setting fom_user:selfregister in the *doctrine.yaml* to true.

fom_user:
 selfregister: false # true/false

The Login dialog contains a *Register* button. This opens a page where the user can type in their name, password and email address.

Registration
User name *
Email *
Choose password *
Confirm password *
▶ Back to login
Register

After that, the user gets a confirmation mail to complete the registration. Until then, Mapbender will handle the user as inactive. The text of the confirmation mail can be customized in the /FOM/UserBundle/Resources/translations/messages.en.xlf file.

Activation of users

Users can be set activated or deactivated by Administrators with the *Edit* right. For this purpose, an **activated** checkbox exists in the Edit User dialog. A user with administration rights cannot activate or deactivate himself.

dit User	
ase data Profile Groups Security	
User name *	
E-Mail *	
John.doe@mapbender.org Choose password	
Confirm password	
activated	
Save	Cancel

A user who is deactivated cannot login into Mapbender anymore until re-activation. Users who self-registered but did not approve the activation email can be activated by an administrator.

Assign permission management to users or groups

- 1. Go to **Security** [] **Global Permissions**.
- 2. Choose Permission management.
- 3. Add users or groups via the **Add users and groups** button. This will assign the *Global Permission Management* right.
- 4. You have now assigned a user/group controlling options over other user accounts.
- 5. With this permission, users and groups can assign rights to other users and groups via **Security Users** or **Security Groups**.

Login Failures

Login failures are responded with the Message "Bad credentials". For security reasons it is not shown if the error is based on a wrong username or a wrong password. Login failures will not lock the account indefinitely after four attempts. Rather the account will be locked for a given period of time.

The doctrine.yaml allows to adjust this behaviour:

```
fom_user:
    # Allow to create user log table on the fly if the table doesn't exits.
    # Default: true
    auto_create_log_table: true
    # Time between to check login tries
    login_check_log_time: "-5 minutes"
    # Login attemps before delay starts
    login_attempts_before_delay: 3
    # Login delay after all attemps are failed
    login_delay_after_fail: 2 # Seconds
```

- **auto_create_log_table:** Backwards compatibility parameter (default: true).
- login_check_log_time: Cleaning of the login-failure table (default: -5 minutes)
- login_attempts_before_delay: Number of login failures before the login delay starts (default: 3)
- login_delay_after_fail: Number of seconds of the login-delay (default: 2).

4.3.2 Groups and Roles

Groups

Groups are individually created database entities that can be assigned to one or more users. Their primary use case is to distribute a set of permissions which are assigned to every user of that group. Assuming that an account has the permission, groups will be created and configured via Security [] Groups [] Add new group. Mapbender offers an overview over every group at the same place:

currey			
ers Groups Glo	bal Permissions		
- Add new group		Filter	
Title	Description		
Title Application editors	Description This group includes all accounts that are authorized to configure Mapbender applications.	* 🛙	J
Title Application editors Test accounts	Description This group includes all accounts that are authorized to configure Mapbender applications. A group that includes all accounts created for testing purposes.	¢ 0 ¢ 0	1
Title Application editors Test accounts Mapbender Team	Description This group includes all accounts that are authorized to configure Mapbender applications. A group that includes all accounts created for testing purposes. This group includes all accounts of the Mapbender team.	¢ 0 ¢ 0 ¢ 0	1
Title Application editors Test accounts Mapbender Team A-Team	Description This group includes all accounts that are authorized to configure Mapbender applications. A group that includes all accounts created for testing purposes. This group includes all accounts of the Mapbender team. I love it when a plan works.	* @ * @ * @	1 1 1

Roles

Roles are used for global permission checks, even if no other permission structure (e.g., a group membership) is involved. They can be used as security identities for domain objects. In Mapbender, there are currently two roles for permission allocation available:

- **Public Access**: Sets global permissions for users which are browsing Mapbender without an individual account.
- All authenticated users: Gives global permissions for one or more entities to all users that are logged in while working with Mapbender.

Depending on the context, roles can be assigned authorizations in the Security tab of an application or under Global permissions. An individual application could be secured as follows:

e data Layouts	Layersets (CSS Security				
						+
Filter		View 🕑	Edit 🕑	Delete	Permission Management 🕑	
Public Access		View	Edit	Delete	Permission Management	Û
🕋 All Registered Users		View	Edit	Delete	Permission Management	Û

Hint: Assign rights to an entity via Security [] Global Permissions.

4.3.3 Permission management

An authorized user can manage global or individual permissions to secure the domain objects. Mapbender provides the following permission rights:

- Create: Create a new object
- View: View an existing object
- Edit: Edit an existing object
- Delete: Delete an existing object
- Manage Permissions: Allow permission editing
- Refresh: Allow source refreshing

Add users and groups to this area via **Security** [] **Global permissions** [] **Permission management** so that they have access to manage permissions.

CHAPTER

FIVE

CUSTOMIZATION / TIPS AND TRICKS

5.1 How to create your own Template?

Mapbender comes with application templates out of the box. You can find them in the Mapbender Core-Bundle: */application/mapbender/src/Mapbender/CoreBundle/Template*. But usually you want to use your own templates with your own corporate design. To prevent overwriting your custom templates after an Mapbender upgrade you should create an extra bundle to safely store your custom files. You can also change the style of your application with the built-in *CSS-Editor*.

Steps for including your templates:

- Create your own bundle,
- Create a new namespace,
- Create a template PHP-file to register your template,
- Create your own Twig-file,
- Create your own CSS-file(s),
- Use your template.

To help you, we prepared a Workshop/DemoBundle, which can be used not only for application templates, but also for customizing the administration interface. For the following steps, you can download the files from the Workshop bundle.

5.1.1 Create your own bundle

User bundles are stored in the *src*-directory. This is how the structure can look like:

```
src/Workshop/DemoBundle/
WorkshopDemoBundle.php
/Resources
/public
demo_fullscreen.css
/image
workshop.ico
workshop_logo.png
print.png
```

(continues on next page)

/v	/iews
	/Template
	fullscreen_demo.html.twig
/Template	
	DemoFullscreen.php

The following files have to be altered for design changes:

- twig-file: to change the structure (e.g. delete a component like the sidebar),
- css-file: to change colors, icons, fonts.

5.1.2 Create a new namespace

The *WorkshopDemoBundle.php* file creates the namespace for the bundle and refers to the template and to your css files.

```
<?php
namespace Workshop\DemoBundle;
use Mapbender\CoreBundle\Component\MapbenderBundle;
class WorkshopDemoBundle extends MapbenderBundle
{
    public function getElements()
    {
        return array(
              'Workshop\DemoBundle\Element\MapKlick',
        //
        );
    }
   public function getTemplates()
    {
        return array('Workshop\DemoBundle\Template\DemoFullscreen');
    }
}
```

5.1.3 Create your own template file

In our example, the template file is called *DemoFullscreen.php*. You can find it at *src/Workshop/DemoBundle/Template/DemoFullscreen.php*. In the templates file, you define the name of your template, the regions that you want to provide and refer to a twig file.

```
<?php
namespace Workshop\DemoBundle\Template;
use Mapbender\CoreBundle\Template\Fullscreen;
class DemoFullscreen extends Fullscreen
{
    protected static $title = "Fullscreen Template Workshop";
    protected static $regions = array('toolbar', 'sidepane', 'content', 'footer');
    protected static $regionsProperties = array(</pre>
```

```
(continues on next page)
```

```
'sidepane' => array(
          'tabs'
                     => аггау(
              'name' => 'tabs',
              'label' => 'mb.manager.template.region.tabs.label'),
          'accordion' => array(
              'name' => 'accordion',
              'label' => 'mb.manager.template.region.accordion.label')
      )
  );
  protected static $css
                                      = array(
      '@MapbenderCoreBundle/Resources/public/sass/template/fullscreen.scss',
      '@WorkshopDemoBundle/Resources/public/demo_fullscreen.scss',
  );
  protected static $js
                                      = arrav(
      '@FOMCoreBundle/Resources/public/js/frontend/sidepane.js',
      '@FOMCoreBundle/Resources/public/js/frontend/tabcontainer.js',
      '@MapbenderCoreBundle/Resources/public/mapbender.container.info.js',
      '/components/jquerydialogextendjs/jquerydialogextendjs-built.js',
      "/components/vis-ui.js/vis-ui.js-built.js"
  );
public function getTwigTemplate()
{
    return '@WorkshopDemoBundle/Resources/views/Template/demo fullscreen.html.twig';
}
```

5.1.4 Create your own twig-file

You find the twig-files at the following path:

• application/mapbender/src/Mapbender/CoreBundle/Resources/views/Template

The easiest way to create your own twig file is to copy an existing twig, save it under a new name and change the content like colors. Use the existing template from *mapben-der/src/Mapbender/CoreBundle/Resources/views/Template/fullscreen.html.twig* and copy it to *fullscreen_demo.html.twig*.

5.1.5 Create your own CSS file

Create an empty css-file and fill it with content. You only have to define the parts that have to look different from the default style of the element. Developer tools can help you to find out the styles you want to change.

Your file could be named *src/Workshop/DemoBundle/public/demo_fullscreen.css* and have the following definition:

```
.toolBar {
   background-color: rgba(0, 29, 122, 0.8) !important;
}
.toolPane {
   background-color: rgba(0, 29, 122, 0.8) !important;
}
```

(continues on next page)

```
.sidePane {
 overflow: visible;
 background-image: url("");
 background-color: #eff7e9;
}
.sidePane.opened {
    width: 350px;
}
.logoContainer {
 background-color: white !important;
  background-image: url("") !important;
  -webkit-box-shadow: 0px 0px 3px #0028AD !important;
  -moz-box-shadow: 0px 0px 3px #0028AD !important;
  box-shadow: 0px 0px 3px #0028AD !important;
}
.sidePaneTabItem {
   background-color: #0028AD;
}
.layer-opacity-handle {
    background-color: #0028AD;
}
.mb-element-overview .toggleOverview {
    background-color: #0028AD;
}
.button, .tabContainerAlt .tab {
    background-color: #0028AD;
}
.iconPrint:before {
  /*content: "\f02f"; }*/
 content:url("image/print.png");
}
.popup {
 background-color: #eff7e9;
 background-image: url("");
}
.pan{
 background-color: rgba(0, 93, 83, 0.9);
}
```

The result of these few lines of css will look like this:



When you open your new application, a css-file will be created at:

• web/assets/WorkshopDemoBundle_demo_fullscreen_css.css

If you do further edits at your css file, you may have to delete the generated css file in the assets directory to see the changes. You should also clear the browser cache.

sudo rm -f web/assets/WorkshopDemoBundle__demo_fullscreen__css.css

5.1.6 Style the administrational pages

Please change the following css-files for the *Backend* pages:

- login.css: Change the design of the login page,
- manager.css: Change the design of the administration pages (e.g. Application),
- password.css: Change the design of the password pages (e.g. Reset Password).

You only have to define the parts that have to look different than the default page style. Developer tools can help you to find out the styles you want to change.

Referencing the CSS-files is possible with FOMManagerBundle and FOMUserBundle. They must be filed under *app/Resources/*. The already contained twig-files overwrite the default settings if configured correctly (Requirements from *manager.html.twig* file). Alternatively, it is possible to copy a twig-file and adjust it afterwards.

cp fom/src/FOM/ManagerBundle/Resources/views/manager.html.twig app/Resources/ →FOMManagerBundle/views/

5.1.7 Register your bundle in config/bundles.php

Add write access to the *public* directory for your webserver user, if need be:

chmod ug+w public

Update the *public* directory. Each bundle has its own assets - CSS files, JavaScript files, images and more - but these must be copied into the public *web* folder:

bin/console assets:install public

Alternatively, as a developer, you might want to use the symlink switch on that command to symlink instead of copy. This will make editing assets inside the bundle directories way easier.

bin/console assets:install public --symlink --relative

Now your template should show up in the template list when you create a new application.

5.1.8 How to use a new template

There are different ways of how to use the new template:

Usage in YAML applications

You can adjust the YAML-applications in *config/applications* and change the template parameter.

```
template: Workshop\DemoBundle\Template\DemoFullscreen
```

Usage in new applications from the backend

If you create a new application in the administration interface of Mapbender, you can choose the new template.

Usage in an existing application

For existing applications, you can change the parameter in the Mapbender database in the column **tem-plate** of the table **mb_core_application**.

For the **WorkshopDemoBundle**, you can change the entry from Mapbender\CoreBundle\Template\ Fullscreen to Workshop\DemoBundle\WorkshopDemoBundle.

5.1.9 Usecases

Q: How do I change the logo, the title and the language?

A: This and more tips can be found under YAML Configuration (Configuration and Application files).

5.1.10 How do I change the buttons?

Mapbender uses 'Font Awesome Icons' font icon collection:

In your CSS file, you can refer to a font images like this:

```
.iconPrint:before {
   content: "\f02f";
}
```

If you want to use an image, you could place it in your bundle and refer to it like this:

```
.iconPrint:before {
   content:url("image/print.png");
}
```

5.1.11 Try this out

- you can download the Workshop/DemoBundle here,
- change the color of your icons,
- change the size of your icons,
- change the color of the toolbar,
- use an image instead of a font-icon for your button,
- move the position of your overview to the left,
- Have a look at the workshop files to see how it works.

5.2 YAML Configuration (Configuration and Application files)

The following configuration files are under the *config/* folder and its subfolders.

5.2.1 doctrine.yaml

- **fom_user.selfregistration**: To enable or disable self-registration of users, change this parameter. You have to define self_registration_groups, so that self-registered users are added to these groups automatically, when they register. They will get the rights that are assigned to these groups.
- **fom_user.reset_password**: In the same way the possibility to reset passwords can be enabled or disabled.
- **framework.session.cookie_httponly**: For HTTP-only session cookies, make sure the framework.session.cookie_httponly parameter is set to true.

Database configuration

The files .env.local and doctrine.yaml are needed to configure databases in Mapbender. In .env.local, (multiple) variables and definitions for database connection(s) can be defined. These variables are being processed in doctrine.yaml.

Note: Every database defined in *.env* needs to have a placeholder in *doctrine.yaml*:

```
doctrine:
   dbal:
        default_connection: default
                                                        # Database connection, used as standard in
→ Mapbender (``default_connection: default``).
        connections:
           default:
           url: '%env(resolve: MAPBENDER DATABASE URL)%'# Placeholder which resolves the environment
→ variable in parameters.yaml.
           persistent: true
                                                        # Parameter specifying if the database
⇔connection should be established continuously.
           charset:
                       UTF8
                                                        # Coding of the database.
           #server_version: '15'
                                                        # Important: You MUST configure your server
\leftrightarrow version, either here or in the DATABASE_URL env var (see .env file).
           logging: "%kernel.debug%"
                                                        # Option, SQLs won't be logged (standard:
→%kernel.debug%). `More information: <http://www.loremipsum.at/blog/doctrine-2-sql-profiler-in-
→debugleiste>`
            profiling: "%kernel.debug%"
                                                        # Profiling SQL requests. This option can be
→turned of in production. (standard: %kernel.debug%)
```

Use of several databases

Example with two database connections in *doctrine.yaml*:

```
doctrine:
    dbal:
        default_connection: default
        connections:
            # database connection default
            default:
                url: '%env(resolve:MAPBENDER_DATABASE_URL)%'
                charset: UTF8
                #server_version: '15'
                logging: "%kernel.debug%"
                profiling: "%kernel.debug%"
                # database connection geodata_db
```

(continues on next page)

```
geodata_db:
    url: '%env(resolve:GEOBASIS_DATABASE_URL)%'
    persistent: true
    charset: UTF8
    logging: '%kernel.debug%'
    profiling: '%kernel.debug%'
    # IMPORTANT: You MUST configure your server version,
    # either here or in the DATABASE_URL env var (see .env file)
    #server_version: '15'
```

5.2.2 .env or .env.local file

This file handles necessary environmental variables:

Database

The files *.env* and *doctrine.yaml* are used to configure database connections in Mapbender. In *.env*, (multiple) variables for database connection(s) can be defined. The *.env* is overwritten by *.env.local*. This is read by *doctrine.yaml*. Several database connections can also be defined in *doctrine.yaml*. An alias is assigned to each database connection.

Example: Database configuration in *.env.local* with the default database variable, if the pre-installed SQLite database is used:

MAPBENDER_DATABASE_URL="sqlite:///%kernel.project_dir%/var/db/demo.sqlite"

When using PostgreSQL (e.g. for the use with *Search Router*), use the following configuration instead:

Use of several databases

Mapbender also allows you to use several databases. This is recommended when integrating geodata. These should be stored separately from the Mapbender database. You need a second database for geo data search (with SearchRouter) and data collection (Digitizer). The default database connection (default_connection: default) is used by Mapbender.

If you want to use another database, you just have to define a database connection with a different name in your *.env.local* file. Now, you can refer to the database *search_db* in the elements SearchRouter and Digitizer.

To learn more about this structure, visit the Symfony documentation. Mapbender uses Doctrine. Doctrine is a collection of PHP libaries (Doctrine project).

Mailer

The mailer information is defined in the .env.local file via the MAILER_DSN variable.

```
#MAILER_DSN=smtp://user:pass@smtp.example.com:25
MAILER_DSN=null://null
```

The configuration will be called via the *fom.yaml* file:

```
fom_user:
    selfregister: false
    reset_password: true
    max_reset_time: 1
    mail_from_address: info@mapbender.org
    mail_from_name: Mapbender Team
```

Hint: The functions 'Self-Registration' and 'Reset password' need a mailer. More information in chapter *Users*.

5.2.3 parameters.yaml

The following fundamental Mapbender parameters are specified here.

Disclaimer



A disclaimer can be added through the use of site links.

```
mapbender.sitelinks:

- link: https://mapbender.org/en/legal-notice/  # Link URL

text: Imprint & Contact  # Link[]

→ text

- link: https://mapbender.org/en/privacy-policy/

text: Privacy Policy

- link: https://doc.mapbender.org/

text: Documentation
```

Disabling Elements

Disabling individual elements can be configured using the following parameter:

mapbender.disabled_elements:
Customizing icons

By setting the following parameters, you can enable specific customization of icons:

- mapbender.icons.disable_default (default: false).
 - When set to *true*, the default icons from the Mapbender namespace are disabled in the button edit form. These include the icons About, Area Ruler, Feature Info, Image Export, Layer tree, Legend, Line ruler, and Polygon. These are used, for example, for the similarly named elements: *About Dialog, Line/Area Ruler, FeatureInfo, Image Export, Layertree, Legend, Digitizer,* and *Sketches*.
- 2. mapbender.icons.disable_default_fa (default: false).
 - When set to *true*, the default Font Awesome icons are disabled in the button edit form. This applies to all other available icons that are not in the Mapbender namespace.
- 3. mapbender.icons.custom (default: ~).
 - Allows adding more icons from FontAwesome (a list of freely available icons can be found on the Font Awesome homepage).
 - The parameter is an array of objects containing three keys:
 - name: Identifier for this icon, e.g., for usage in yaml-defined applications.
 - *title*: Description of the icon as shown in the selection menu in the button edit form.
 - *class*: Full class name (including "fa") of the icon. Copy it from the lower part of the popup when you click on the icon on the Font Awesome homepage.

With these configuration options, you can customize the icons in Mapbender to suit your requirements. Here's an example:

Language settings

Mapbender is automatically adjusted to your browser's language. Yet it is also possible to set your preferred language via the *fallback_locale* parameter. If a translation of your browser's language is missing in Mapbender, it will take the defined language.

The locale can only be set for the entire Mapbender installation (not for single applications).

Available language codes are:

- en for English (default)
- de for German
- es for Spanish
- fr for French
- it for Italian

- nl for Dutch
- pt for Portugese
- ru for Russian
- tr for Turkish
- uk for Ukrainian

Configuration example:

fallback_locale:	en
locale:	en
secret:	ThisTokenIsNotSoSecretChangeIt

You also can force Mapbender to use the language defined for the parameter locale to be used. To do this, add mapbender.automatic_locale: false.

```
mapbender.automatic_locale: false
fallback_locale: en
locale: es
secret: ThisTokenIsNotSoSecretChangeIt
```

More information in *Translation in Mapbender*.

Logo and branding

In *parameters.yaml*, you can refer to your own logo and to an alternative image for the login page. This change has a global impact on the whole Mapbender installation.

```
branding.project_name: Geoportal powered by Mapbender
branding.project_version: 1.0
branding.logo: ./bundles/mapbendercore/image/OSGeo_project.png
branding.favicon: ./application/public/brand-favicon.ico
branding.login_backdrop: ./bundles/mapbendercore/image/login-backdrop.jpg
```

The files must be accessible under application/public.

Project name

The name of the project (default: Mapbender) can be changed in *parameters.yaml*. The change has a global impact on the whole Mapbender installation.

branding.project_name: Geoportal

Warning: In *parameters.yaml*, tabulators may not be used for indentation. Instead, you need to use the space bar.

Proxy settings

If you use a proxy, you need to change parameters.yaml.

Hint: OWSProxy3 is a transparent Buzz-based proxy that uses cURL for connection to web resources via/without a proxy server.

Configuration example:

<pre># OWSProxy Configuration</pre>	
<pre>ows_proxy3_logging: false</pre>	# logging of requests, default is false, true logs in table
⇔owsproxy_log	
<pre>ows_proxy3_obfuscate_client_ip: true</pre>	# obfuscats a client ip, default is true, true will hide the
\hookrightarrow last byte of the client's ip address	
<pre>ows_proxy3_host: myproxy</pre>	# proxy definition for connnection via a proxy server. Host
⇔name of the proxy server	
ows_proxy3_port: 8080	# proxy definition for connnection via a proxy server. Port
⇔name of the proxy server	
<pre>ows_proxy3_connecttimeout: 60</pre>	
<pre>ows_proxy3_timeout: 90</pre>	
ows_proxy3_user: ~	# user name for proxy server (set user for proxy server if
\hookrightarrow needed)	
ows_proxy3_password: ~	<i># password for proxy server (set password for proxy server if</i>
\hookrightarrow defined)	
ows_proxy3_noproxy:	<pre># list of hosts for connnections without proxy server</pre>
- 192.168.1.123	

SSL certificate

For productive environments, it is important to install a SSL certificate. After that, set the parameters. cookie_secure variable in your *parameters.yaml* to true. This ensures that the Login cookie is only transmitted over secure connections.

Overriding JavaScript and CSS/Sass Resources

To manually override JavaScript and CSS/Sass resources, and as an alternative to *overriding in the bundle*, you can add the following to your paramaters.yaml file:

```
mapbender.asset_overrides:
    "@MapbenderCoreBundle/Resources/public/sass/element/featureinfo.scss": "@@MyBundle/Resources/public/
    →sass/element/custom_featureinfo.scss"
```

Note: Please note that the @ sign in the replacement key must be escaped with an additional @@ sign.

5.2.4 YAML Application files

YAML application files are stored under *applications/* (underneath *config/*!). There are three files preimplemented as example applications:

- Mapbender Demo (*mapbender_user*)
- Mapbender Demo Basic (*mapbender_user_basic*)
- Mapbender Mobile Demo (mapbender_mobile)

If you do not want the three example applications to be visible, you can adjust the published variable as follows.

```
parameters:
    applications:
    mapbender_mobile:
    [...]
    published: false
```

Then, clear the *Mapbender cache* and your browser cache. After that, the applications will not be visible for users.

Hint: The root user can always see unpublished applications.

It is also possible to remove the applications from the applications folder. Repeat the cache clearing process afterwards.

In the same way, new YAML applications can be placed in the folder and will be automatically recognized by Mapbender.

5.2.5 Mapbender Demo Map

This is the main Demo application. Should be used for a desktop based application.

Detailed descriptions of the elements at *Elements*.

5.2.6 Mapbender Demo Map basic

Differences to the main Demo Map:

Toolbar Contains elements from the sidepane of the first demo application.

Sidepane Has no elements pre-implemented.

Map area Uses a compact *Navigation Toolbar* without the zoom slider. Includes the *Simple Search*. Detailed descriptions of the elements at *Elements*.

5.2.7 Mapbender mobile

For a mobile template on smartphones and tablets.

5.2.8 Export/import YAML application files with the backend

Export

You can export applications as JSON files under **Applications** [] **Export**.

You can locate the export button within the application overview page. Find it in the application's button menu.



Import

Under **Applications** [] **Import**, an export file can be imported into a Mapbender installation.

To do this, first select the Create Application button. Then click on the Import button:



Then, use the Import mask to load an import file as an application.

Import	
Import file*	
Browse	No file selected.

5.2.9 Export/import/clone YAML application files over the console

Please go to *Application Export, Import & Cloning* to see the console commands. Find a few introductional words about exporting and importing applications over the console below.

Export

Applications can be exported as .json or .yaml file over the console.

A YAML file that has been exported over the console cannot be placed under *applications/* to be imported in a Mapbender installation. The YAML format that is produced by exporting over the console is different from the YAML format of the files under *applications/*.

Import

YAML files that have been exported over the user interface or console can be imported over the console.

Clone

Clone/Copy an existing application.

5.3 bin/console commands

Mapbender provides commands that can be executed via the command line. Some of the commands are provided by the Symfony components, others belong to Mapbender.

Some useful commands are described in the following document.

Make sure you are in the correct directory (above the app directory)

- mapbender/application (installation via GitHub)
- mapbender (installation via package)

5.3.1 Help command

The parameter --help displays the help message for every command, for example:

bin/console mapbender:user:create --help

5.3.2 Application Export, Import & Cloning

bin/console mapbender:application:export

You can export an application as JSON- or YAML-file. In the command you have to add the Url title (slug) of the application and define the export file.

For .json files (also available via browser):

```
bin/console mapbender:application:export mapbender_user_db --format=json > export.json
```

For .yaml files (only via command line):

```
bin/console mapbender:application:export mapbender_user_db --format=yaml > export.yaml
```

bin/console mapbender:application:import

You can import an application from a JSON or YAML-file. Mapbender will automatically choose a new name if the name already excists.

```
bin/console mapbender:application:import export.json
```

```
Imported 1 applications
* mapbender_user_db_imp2
```

bin/console mapbender:application:clone

In the application backend, you can also clone an existing application. This will generate a new application with a suffix added to the application name. For yaml applications, a *_db* suffix is appended, while for applications from the database, a *_imp* suffix is added.

```
bin/console mapbender:application:clone mapbender_user_yml
```

5.3.3 User administration

bin/console mapbender:user:create

Command to create a new user on the command line. User name, email and password are mandatory. User name and email have to be unique.

Update user settings

Information for a user can be updated:

- email
- password

The user name cannot be changed.

```
bin/console mapbender:user:create --update --password <password> --email <email> <name>
```

```
bin/console mapbender:user:create --update --password mypassword8910 --email max.mustermann@mapbender.

→org 'Max Mustermann'
```

bin/console fom:user:resetroot

Command to create or update the root account. User name, email and password must be assigned for creation.

During the update, the unique assignment is made via the already existing ID, therefore all three parameters mentioned above can be changed.

```
bin/console fom:user:resetroot
```

bin/console fom:user:resetroot --username="root" --password="root" --email="root@example.com"

bin/console mapbender:user:list

Command to list all existing users with their ID and user name and the time of creation.

```
bin/console mapbender:user:list
User #3 name: max mustermann since 2019-10-14 12:10:44
```

5.3.4 Database

bin/console mapbender:database:upgrade

Command to update the Mapbender database.

```
bin/console mapbender:database:upgrade
Updating map element configs
Found 28 map elements
28/28 [=======] 100%
Updated 28 Map elements
Exiting now
```

bin/console doctrine:database:create

The command is used only once during installation and creates the administration database for Mapbender. The database connection can be found in the parameters.yaml file.

bin/console doctrine:database:create

bin/console doctrine:schema:create

The command is used only once during installation and creates the database schema, which means that the tables required by Mapbender are created.

bin/console doctrine:schema:create

bin/console doctrine:schema:update

The command is needed on Mapbender update. It generates the SQL needed to synchronize the database schema to the new Mapbender version.

Note: The Mapbender database should be an independent database. Your geodata should be stored other separate databases. While updating the Mapbender database, tables that are not covered by a doctrine schema might be deleted. Geodata in independent databases is not affected by this.

bin/console doctrine:schema:update --complete --dump-sql
bin/console doctrine:schema:update --complete --force

• **--dump-sql** Shows changes in the database schema.

• --force Executes the changes in the database schema.

bin/console doctrine:schema:validate

Validate whether that the database is up-to-date.

```
bin/console doctrine:schema:validate
[Mapping] OK - The mapping files are correct.
```

5.3.5 Print

bin/console mapbender:print:queue:next

The queued print is disabled by default because it requires some external integration setup. To run print jobs via the command line, the following parameter must be added to the parameters.yaml file and set to TRUE to enable queued printing.

mapbender.print.queueable: true

Read more about the general characteristics of queued print at *Queued Print*. Also here

The print assistant is then updated in the *Backend* of Mapbender and two new lines appear: mode and queue. Mode is set to "queue" and queue is set to "global", if the print jobs are expected to be accessible to all colleagues. The new tab "Recent jobs" (which shows your scheduled print jobs) appears in the print client pop-up window.

To run the jobs the following commands can be used.

bin/console mapbender:print:queue:next

The command mapbender:print:queue:next executes the next print job in the queue. For a potentially infinite process, the following options can be set to 0.

bin/console mapbender:print:queue:next --max-jobs=0 --max-time=0

Optional parameters:

- **--max-jobs** Sets a limit for the maximum number of processed jobs.
- --max-time Sets a limit for the maximum time for the command to process.

bin/console mapbender:print:queue:rerun

This command reruns a print queue job. The ID for the job must be set.

bin/console mapbender:print:queue:rerun 1

Starting processing of queued job #1

PDF for queued job #1 rendered to /data/mapbender/application/app/../web/prints/mapbender_ →20191104103745.pdf

bin/console mapbender:print:queue:dumpjob

This command dumps the queued print job from the database to JSON or YAML. The ID of the print job is required. This ID can be determined from the open print queue in the Mapbender application.

```
bin/console mapbender:print:queue:dumpjob [options] [--] <id>
bin/console mapbender:print:queue:dumpjob 2 > print configuration.json
    bin/console mapbender:print:queue:dumpjob 2
{
    "template": "a4portrait",
    "quality": "288",
"scale_select": "25000",
    "rotation": "-20",
    "extra": {
        "title": "My Title"
    },
    "lavers": {
        "0": {
            "type": "wms",
            "sourceId": "8"
            "url": "https:///osm-demo.wheregroup.com//service? SIGNATURE=31
→%3AIHZNT0zPZhFG95dN3Q0zsizaDwA&TRANSPARENT=TRUE&FORMAT=image%2Fpng&VERSION=1.3.0&EXCEPTIONS=INIMAGE&
→SERVICE=WMS&REQUEST=GetMap&STYLES=&LAYERS=osm& OLSALT=0.3940783483836241&CRS=EPSG%3A25832&BBOX=363375.
→ 30907721.5626747.0157598.368124.31589362.5620823.2546257&WIDTH=512&HEIGHT=512".
            "minResolution": null.
            "maxResolution": null,
            "order": 0,
            "opacity": 1.
            "changeAxis": false
        },
        "1": {
            "type": "wms",
            "sourceId": "7"
            "url": "https:\/\/\/wms.wheregroup.com\/cgi-bin\/mapbender_user.xml?_SIGNATURE=26%3Atq6ae-
→UqhnZLMjiQlLrj-wCHiOI&TRANSPARENT=TRUE&FORMAT=image%2Fpng&VERSION=1.3.0&EXCEPTIONS=INIMAGE&
→SERVICE=WMS&REQUEST=GetMap&STYLES=&LAYERS=Mapbender User& OLSALT=0.6831931928241708&CRS=EPSG%3A25832&
→BB0X=363375.30907721,5626747.0157598,368124.31589362,5620823.2546257&WIDTH=2400&HEIGHT=1141",
            "minResolution": null.
            "maxResolution": null,
            "order": 0,
            "opacity": 0.85,
            "changeAxis": false
        },
        "2": {
            "type": "wms"
            "sourceId": "7"
            "url": "https:\/\/wms.wheregroup.com\/cgi-bin\/mapbender_user.xml?_SIGNATURE=26%3Atq6ae-
→UqhnZLMjiQlLrj-wCHiOI&TRANSPARENT=TRUE&FORMAT=image%2Fpng&VERSION=1.3.0&EXCEPTIONS=INIMAGE&
SERVICE=WMS&REQUEST=GetMap&STYLES=&LAYERS=Mapbender_Names&_OLSALT=0.6831931928241708&CRS=EPSG%3A25832&
→BB0X=363375.30907721,5626747.0157598,368124.31589362,5620823.2546257&WIDTH=2400&HEIGHT=1141",
            "minResolution": null.
            "maxResolution": null,
            "order": 1,
            "opacity": 0.85,
            "changeAxis": false
        }
```

(continues on next page)

(continued from previous page)

```
},
    "width": 1920,
    "height": 913,
    "center": {
        "x": 365749.81248542,
        "y": 5623785.1351928
    },
    "extent": {
        "width": 4749.006816409994,
        "height": 5923.761134099215
    },
    "overview": {
        "layers": {
            "0": "https:////osm-demo.wheregroup.com//service?_signature=31
→%3AIHZNT0zPZhFG95dN3Q0zsizaDwA&TRANSPARENT=TRUE&FORMAT=image%2Fpng&VERSION=1.3.0&EXCEPTIONS=INIMAGE&
→SERVICE=WMS&REQUEST=GetMap&STYLES=&LAYERS=osm&CRS=EPSG%3A25832&BBOX=350757.32820012,5616536.5348653,
→377637.46662208,5629318.6006879&WIDTH=250&HEIGHT=125"
        },
        "center": {
            "x": 364197.3974111.
            "y": 5622927.5677766
        },
        "height": 78125,
        "changeAxis": false
    },
    "mapDpi": 90.714,
    "extent_feature": {
        "0": {
            "x": 362505.8322437394,
            "y": 5625755.14826519
        },
        "1": {
            "x": 366968.4389051802.
            "v": 5627379.404257199
       },
"2": {
            "x": 368994.48453732743,
            "y": 5621812.889632087
       },
        "3": {
            "x": 364531.877875887,
            "v": 5620188.63364008
        },
        "4": {
            "x": 362505.8322437394,
            "y": 5625755.14826519
       }
    },
    "userId": null,
    "userName": null,
    "legendpage_image": {
        "type": "resource",
        "path": "images //legendpage_image.png"
   }
}
```

bin/console mapbender:print:runJob

Command to run a print job from a saved job definition. The JSON file created with the previously described command (bin/console mapbender:print:dumpjob) will create a pdf print output.

bin/console mapbender:print:runJob print_configuration.json /tmp/print.pdf

bin/console mapbender:print:queue:repair

If a print job in the queue has crashed, e.g. a WMS service is not accessible, printing cannot be performed. The command resets the status of the print jobs so that they can be executed again.

bin/console mapbender:print:queue:repair

bin/console mapbender:print:queue:clean

This command purges old jobs from the print queue (database and files). This includes created PDFs as well as corresponding database entries for the print jobs which are listed in the table called "mb_print_queue". With the command the expiring age can be set, for example, 20 can be used to delete all jobs older than 20 days.

```
bin/console mapbender:print:queue:clean 20
```

Print queue clean process started. Deleted 0 print queue item(s)

bin/console mapbender:print:queue:gcfiles

gcfiles means "garbage collection files". This command deletes unreferenced files from print queue storage path. This can happen, for example, if a job is deleted from the database or the file path to the PDFs is no longer up-to-date.

```
bin/console mapbender:print:queue:gcfiles
```

No unreferenced local files found

5.3.6 Mailer

bin/console debug:config framework mailer

Command displays the configured mailer(s)

bin/console debug:config framework mailer

5.3.7 Server

symfony server:start -no-tls

As a prerequisite for the Symfony development server, the Symfony CLI must be installed. Following a successful installation, the command launches the development server. In this mode, it is possible to open your local Mapbender. The terminal additionally logs the status of the server while it is active.

You can stop the server again with Control -C.

Note: The Symfony development server may have limitations that reduce the performance of the application in certain cases. It should be used for testing purposes.

```
symfony server:start --no-tls
```

```
[OK] Web server listening
The Web server is using PHP CLI 8.2.10
http://127.0.0.1:8000
```

Hint: It is still possible to define the application environment with a preceding APP_ENV=prod or APP_ENV=dev.

```
APP_ENV=prod symfony server:start --no-tls
```

5.3.8 Clear cache

bin/console cache:clear

The command clear the cache directory.

Dev:

```
bin/console cache:clear --env=dev
```

Prod:

```
bin/console cache:clear --env=prod --no-debug
```

5.3.9 WMS Services

bin/console mapbender:wms:add

Adds a new WMS Source to your Mapbender Service repository.

(continues on next page)

```
* * osm-grey OpenStreetMap (grey scale)
Saved new source #76
```

bin/console mapbender:wms:assign

Adds a WMS source instance from the sources repository to a Mapbender application.

```
bin/console mapbender:wms:assign [options] [--] <application> <source> [<layerset>]
```

5.3.10 Configuration

- application: ID or slug of the application,
- source: ID of the WMS service,
- *layerset* (optional): ID or name of the layerset. The default value is *main* or the first layerset in the application.

The following additional options are available:

- **-f, --format** Sets the format for the GetMap request, such as image/png.
- -i, --infoformat Sets the format for the FeatureInfo request, such as text/html.
- **-p, --proxy** Determines whether a proxy is used (true | false).
- -t, --tiled Specifies whether GetMap requests are returned as tiles (true | false).
- **-I, --layerorder** Sets the layer order (standard | reverse) (Note: reverse = QGIS).

bin/console mapbender:wms:parse:url

Command to parse a GetCapabilities document by url. The command can be used to validate a WMS Url.

bin/console mapbender:wms:reload:file

Command to reload (update) a WMS source from given file.

bin/console mapbender:wms:reload:url 76 /var/www/html/service.xml

The following additional options are possible:

- **--deactivate-new-layers** If set, newly added layers will be deactivated in existing instances. Deactivated layers are not visible in the frontend.
- --deselect-new-layers If set, newly added layers will be deselected in existing instances. Deselected layers are not visible on the map by default, but appear in the layer tree and can be selected by users.

bin/console mapbender:wms:reload:url

Command to reload (update) a WMS source from given url.

The following additional options are possible:

- --user=USER Username (basicauth) [default: ""]
- --password=PASSWORD Password (basic auth) [default: ""]
- --deactivate-new-layers If set, newly added layers will be deactivated in existing instances. Deactivated layers are not visible in the frontend.
- --deselect-new-layers If set, newly added layers will be deselected in existing instances. Deselected layers are not visible on the map by default, but appear in the layer tree and can be selected by users.

bin/console mapbender:wms:show

Command to displays layer information of a persisted WMS source. You have to parse the ID of the WMS Source to get the information.

bin/console mapbender:wms:show 76

```
Source describes 3 layers:
 <empty name> OpenStreetMap (WhereGroup)
 * * osm OpenStreetMap
 * * osm-grey OpenStreetMap (grey scale)
```

5.3.11 Other

bin/console mapbender:source:rewrite:host

Use this command to update the hostname in the source URLs, eliminating the need to reload service capabilities.

bin/console mapbender:source:rewrite:host [options] [--] <from> <to>

As usual, the *Help command* shows more options.

Example to update the hostname:

```
bin/console mapbender:source:rewrite:host "http://osm-demo.wheregroup.com" "https://osm-demo.wheregroup.

→ com"
3 modified urls in WMS source #5 / OpenStreetMap (OSM) Demo WhereGroup
Summary:
1 sources changed
3 urls changed
4 sources unchanged
14 urls unchanged
```

bin/console mapbender:config:check

Command to check the system configuration and mapbender requirements. Useful command to determine whether dependencies are compliant and database access works.

bin/console mapbender:config:check

Hint: Please note that config:check will use the php-cli version. The settings may be different from your webserver PHP settings. Please use php -r 'phpinfo();' to show your PHP webserver settings.

The following requirements are checked and displayed:

- Database connections
- PHP Version
- System requirements
- Asset Folders
- FastCGI
- Apache modus (rewrite)
- PHP ini
- loaded PHP extensions
- Directory permissions

bin/console mapbender:version

The command outputs the current version of Mapbender.

bin/console mapbender:version

Mapbender 3.3.4

bin/console debug:config

Command lists all registered bundles (packages) and, if available, their aliases.

bin/console debug:config

5.4 API

Mapbender provides an API that allows you to run several commands.

With the API clients can administrate Mapbender without the need to use the web administration interface. The API provides commands to get information for example about services and it also provides commands to publish or update services.

$\leftarrow \rightarrow \mathbf{C}$ a C	A https://demo.mapbender.org/api/doc	ネ 90% ☆	ତ 🕵 ମ 🕇 ≡
			🙀 NelmioApiDocBundle
	Mapbender API 🚥 🚥		
	Only authorized users have access to this API. A JWT (JSON Web Token) must be obtained by sending a username and password via the 'zapi/login_check' endpoint. This page can be used to test the API. To enable testing, click the Authorize' button and provide the obtained JWT.		
		Authorize	
	login Endpoint for user authentication and obtaining a token	^	
	POST /api/login_check Authenticates a user and returns a JWT	~	
	WITS Endpoints related to WIMS	^	
	GET /api/wms/show Displays layer information of a persisted WMS source	≞ ∨	
	GET /api/wms/reload Reloads a WMX source from given unt	â ~	
	GET /api/wms/add Adds a new WMS source	≙ ∨	
	GET /api/wms/assign Assigns a WMS source to an application	â ~	
	application Endpoints related to applications	^	
	CET /apj/application/clone Creates a copy of an application		
	file-upload Endpoints for handling file uploads	^	
	POST /api/upload/zip Upload a ZUP THE	≞ ~	

5.4.1 Documentation

The API documentation is integrated in every Mapbender installation and it is publicly available via http: //localhost/mapbender/api/doc/

You find examples for each endpoint in the documentation. Please note that you need to login and authorize to run the examples. You also need the right "API" (see ACL).

You can browse through the documentation at the Mapbender demo:

https://demo.mapbender.org/api/doc/

Further information about the API is provided in the Developer Documentation:

https://github.com/mapbender/mapbender/blob/develop/docs/api/setup.md

5.4.2 Apache Authorisation

By default, Apache does not forward the Authorization header to the client for security reasons. However, this is necessary to use the API. The following must therefore be set in the VirtualHost or the configuration:

```
SetEnvIf Authorization "(.*)" HTTP_AUTHORIZATION=$1
```

5.4.3 Configure Upload Directory

You can configure the upload directory using the

```
api_upload_dir: /data/qgis_server_projects/
```

parameter in the *parameters.yaml* file.

5.4.4 Disable the API page from public access

You can disable the public access to the API documentation page by modifing the *security.yaml*. Please change

{ path: ^/api/doc, roles: PUBLIC_ACCESS }

to

{ path: ^/api/doc, roles: ROLE_ADMIN }

CHAPTER

SIX

FAQ - FREQUENTLY ASKED QUESTIONS

6.1 General

6.1.1 Environments: prod and dev

Q: Why does Mapbender offer environments?

A: For productive use, you'll use the **prod** environment. If you develop something (TWIG-files, CSS or JS-files) or want to debug, you should use the **dev** environment. This is because this mode provides more information and error messages.

For further information on the environments, please take a look at the chapter *Start Mapbender in a productive environment*.

6.1.2 Cache

Q: What is the cache and when do I have to clear it?

A: The cache is a small storage area, where Mapbender accesses frequently needed application data. Cache clearing can be useful to refresh your Mapbender installation. You'll delete the contents of the *mapbender/var/cache/* directory, not the folder itself. In detail, the *prod* and - if present - the *dev* directory.

It is no problem to delete these directories. When you run Mapbender again, new files will be stored again in the cache directory.

For further information on the cache, please take a look at the chapter *Production and Development environment and Caching*.

6.1.3 Services and their usage in applications

Q: I would like to know in which applications a specific WMS service is registered. Is there a way to achive that?

A: For users with permission, this information is provided in the *Backend*:

- Go to **Sources** and find your source,
- Select it with a click on Show Metadata, then go to the Applications tab,
- Here, you can see in which application the source is loaded. Moreover, you can see whether the source is integrated as shared or private instance and whether it is activated or inactive.

• Via click on the application title or the source instance, you can switch to the related layerset or instance setting.

If you prefer SQL, you can also take the WMS ID from the Source, replace the <id_of_the_wms> with it in the following SQL and run:

6.1.4 QGIS2Mapbender plugin

Q: Is there a way to publish my QGIS project directly from QGIS as a QGIS Server project and in Mapbender?

A: Yes, there is! From Mapbender version 4.0 you can use the QGIS2Mapbender plugin. It transfers QGIS projects to your server and makes them available as WMS. You can also load your project directly into an application in Mapbender. Take a look at the blog post Mapbender-Anwendungen einfach direkt aus QGIS heraus erstellen. You can find the plugin on GitHub.

6.2 Performance

6.2.1 My application cannot be duplicated

Q: I made a highly complex application and want to duplicate it, but it does not work. Why is that?

A: A possible reason for this is that PHP does not allow a workflow with large files. The problem occurs especially in FastCGI. To fix this, you need to adjust the PHP parameter MaxRequestLen (you can do that in the FastCGI configuration).

```
# mod_fcgi.conf (Windows)
# set value to 2 MB
MaxRequestLen = 2000000
# fcgid.conf (Linux)
# set value to 2 MB
MaxRequestLen 2000000
```

Simultaneously, you should check if the following PHP values are set in your *php.ini*:

```
max_execution_time = 240
memory_limit = 1024M
upload_max_filesize = 2M
```

6.2.2 Adjusting WMS tiling values for ImageExport and PrintClient

Q: My WMS service does not return images in my ImageExport or my PrintClient. Consequently, my output file does not contain layers from the service. What could be causing this?

A: This can have different reasons. Under some circumstances, the requested pixel dimension of a WMS can get too large.

In this case, add the following parameter to your *parameters.yaml* file - note that you have to adjust the default value according to your service.

mapbender.imaageexport.renderer.wms.max_getmap_size: 8192

What does it do? The parameter sets the largest possible WIDTH= and HEIGHT= parameter values for WMS requests generated from the **ImageExport** and **PrintClient** elements. Moreover, the maximum resolution is defined in the MaxWidth or MaxHeight fields of the GetCapabilities request for the service, therefore it's helpful to check the service request for a value to be entered. WIDTH= and HEIGHT= parameters can also be limited separately.

Adjust the width with this parameter and an individual value:

mapbender.imaageexport.renderer.wms.max_getmap_size.x:

Adjust the height with this parameter and an individual value:

```
mapbender.imaageexport.renderer.wms.max_getmap_size.y:
```

6.2.3 Working with large WMS Services with many layers

Q: When I try to use a WMS Service with many layers (> 100) into an application, the configuration of the *Layerset* only takes and presents an incorrect amount of layers. In addition, the WMS instance cannot be saved. Why?

A: To solve the problem, navigate to the php parameter max-input_vars. It defines the number of possible input variables. The default value is 1000 (depending on the php version). For a WMS with many layers, the number of input values is higher than the default value. You have to change the parameter to a higher value (e.g. **2000**).

```
;; 1000 (default)
max_input_vars = 2000
```

6.3 Installation

6.3.1 Attempted to call function "imagecreatefrompng"

Q: I get an error while trying to generate a print output. I have looked into Mapbender's logfile (*var/log/prod.log*) and found something like this:

```
CRITICAL - Uncaught PHP Exception Symfony\Component\Debug\Exception\UndefinedFunctionException:

"Attempted to call function "imagecreatefrompng"

from namespace "Mapbender\PrintBundle\Component"."

at /srv/mapbender-starter/application/mapbender/src/Mapbender/PrintBundle/Component/PrintService.phpD

→line 310
```

A: Please make sure you have installed the php-gd library, because it is necessary for this action. We recommend the installation of the extension before installing Mapbender. However, if you're using a Linux-based system, you can always install it afterwards like this:

sudo apt-get install php-gd

6.3.2 SSL certificate problem

Q: How can I fix my SSL certificate problem?

A: When you get an SSL certificate problem error on loading or updating an OGC WMS data source on Windows-based Mapbender servers, you have to update your *cacert.pem* file and refer to it in your *php.ini*.

The problem can occur while accessing a service via https. It looks like this:

cURL error 60: SSL certificate problem: unable to get local issuer certificate

Note: The file *cacert.pem* that is available online lists all trusted certificate authority. *cacert.pem* is base64-encoded with a definition for all trusted certificate authorities; you can download it from here.

The error above occurs if the file is not referenced in *php.ini* or if *cacert.pem* is not up-to-date.

How to refer to *cacert.pem* in *php.ini*:

curl.cainfo="C:\[your path]\cacert.pem"

openssl.cafile="C:\[your path]\cacert.pem"

If you use an individual self-signed certificate, you can add the information of your certificate authority to *cacert.pem*.

Find further information in the PHP documentation.

6.3.3 Manually install Symfony dependencies

Q: After updating, I need to install a Symfony component for my Mapbender installation. How can I achieve this?

A: It is possible to manually install Symfony components via the command line. This can be done using the following command:

./bin/composer install symfony/your-bundle

Just replace your - bundle with the corresponding component name.

You can find a list of componentens and dependencies in the GitHub Symfony project.

6.3.4 Deprecation Notices at composer or bootstrap script

Q: I get a deprecation warning when I call bootstrap or composer update:

Deprecation Notice: The callback ComposerBootstrap::checkConfiguration declared at /srv//mapbender-starter/application/src/ComposerBootstrap.php accepts a Composer\Script\CommandEvent but post-update-cmd events use a Composer\Script\Event instance. Please adjust your type hint accordingly, see https://getcomposer.org/doc/articles/scripts.md#event-→classes in phar:///srv/mapbender-starter/composer.phar/src/Composer/EventDispatcher/EventDispatcher.php:290

A: This depends on the PHP version the system in running on and occurs on PHP versions < 7. Depending on the Mapbender release, we recommend different PHP versions that do not trigger the notices.

6.4 Developing

6.4.1 Manual updates of modules

Q: How can I checkout a specific branch of the Mapbender module and test it? How can I revert this again? Does Composer help me with that?

A: Alternative 1 (via Git): Go in the directory *application/mapbender* and checkout the specific branch. After your tests, checkout the original branch again. Do not forget to clear the Symfony cache directory.

Alternative 2 (via Composer): Change the entry in composer: "mapbender/mapbender": "dev-fix/meinfix" and do a Composer Update. Keep in mind that with that step all other vendor packages will be updated. To go back, specify the original branch. In addition go back to *application/mapbender* and checkout the original branch.

6.4.2 Overwriting twig templates

Q: What is the process for overwriting twig templates in bundles, and how can I customize the design of specific elements in Mapbender?

A: Twig templates within bundles can be overwritten by placing a twig file with the same name in *templates/bundles/<bundlename>*. If, for example, you want to customise the coordinates display (*Resources/views/Element/coordinatesdisplay.html.twig* within the Mapbender CoreBundle), place a replacement file in *templates/bundles/MapbenderCoreBundle/Element/coordinatesdisplay.html.twig*. The new file will be used instead of the original one.

6.5 Oracle

6.5.1 Adjustments for Oracle database - point and comma

Q: I get an error when I run doctrine: schema: create on Oracle. Why? The error message is:

(continues on next page)

(continued from previous page)

ORA-01722: Invalid number

A: Probably Oracle can't handle the decimal seperators and expects a comma instead of a point (e.g. 1,25 instead of 1.25). This can be adjusted with the following snippet at the end of the *doctrine.yaml* (clear the cache afterwards).

PRIMARY KEY(id))':

This is a relation to a service-class provided by Doctrine. After the connection to Oracle, this class sets Session-Variables (ALTER SESSION) so that PHP and Oracle can work together in a better way.

Reasons might be: Language and regional settings of the operating system (for example Windows), settings of the Oracle-client, settings done during the installation of Oracle.

6.5.2 Rights management in Oracle database

Q: Which rights does the Mapbender user need for the Oracle database?

A: Mapbender needs permission to:

```
- Create Sequence
```

- Create Session
- Create Table
- Create Trigger
- Create View

6.5.3 The access to an Oracle database is too slow

Q: Mapbender seems to have a poor performance while accessing Oracle databases. I noticed this because queries need more time than usual. How can I accelerate the process?

A: There are two parameters in *php.ini* which may tweak the performance of Mapbender with Oracle databases: oci8.max_persistent and oci8.default_prefetch. Adjust these parameters to:

```
oci8.max_persistent = 15
oci8.default_prefetch = 100000
```

Furthermore, change the respective persistent database connection parameter in *doctrine.yaml* to true.

persistent: true

CHAPTER

SEVEN

ARCHITECTURE

7.1 Components

Mapbender is made up of different components. On the server side we use Symfony as a framework which comes along with powerful components like Doctrine, Twig, Monolog and more.

On the client side we use OpenLayers, MapQuery and jQuery & jQuery UI.

We have a Mapbender core bundle with the Mapbender basic functionalities. And more Mapbender bundles which are optional.

We offer a Mapbender Starter package. With the Mapbender Starter package you can set up a Mapbender installation easily.

jQuery UI	OpenLayers			In Symfony2 Bundles are Plugins
jQuery	MapQuery			
Mapbender CoreBundle		Mapbender WMSBundle	FOMBundles	more Bundles
Mapbender Starter				
Symfony2 inkl. Doctrine, Twig, Monolog etc.				

7.1.1 Symfony

Symfony is a full object oriented PHP Web Development Framework. It builds blocks for all modern web application needs. It is a collection of software and a development methodology. It relies on the philosophy of building blocks. It is optimized for speed. It uses Byte Code Cache.

Here is a list of some components Symfony offers:

- Symfony config.php to check the prerequisites
- Symfony Profiler
- Database abstraction via Doctrine
- User authentication, authorization
- Templating via Twig
- Translation using xliff-files
- Logging via Monolog
- Security

The project has a very good documentation:

• TheBook http://symfony.com/doc/current/book/index.html

7.1.2 OpenLayers

OpenLayers is a powerful software for web maps. It supports a lot of data sources and functionality.

Read more about OpenLayers at https://openlayers.org/

You find example applications with OpenLayers at https://openlayers.org/en/latest/examples/

7.1.3 jQuery and jQuery UI

jQuery is a feature-rich JavaScript library. jQuery UI is a set of user interface interactions, effects, widgets, and themes built on top of the jQuery JavaScript Library.

Read more about jquery at http://jquery.com

Read more about jquery UI at http://jqueryui.com/

7.1.4 Mapbender

Mapbender is a collection of bundles. Only the MapbenderCoreBundle and the FOMBundle are mandatory.

There are optional bundles like:

- WMSBundle
- WMTSBundle
- WMCBundle
- MonitoringBundle

CoreBundle

The Mapbender CoreBundle is the base bundle for Mapbender. It offers base classes for applications, elements, layers and more.

It provides jQuery, jQuery UI, OpenLayers and MapQuery for all other Mapbender bundles.

7.1.5 Mapbender Starter

Mapbender Starter is Symfony demo project which uses the Mapbender bundles to showcase a Mapbender application.

It contains demo applications which are defined in the mapbender.yaml with WMS, WMTS. It provides a web interface with authentication which provides the possibility to create applications, create users/groups and build up a service repository.

Mapbender Starter can be used as a boiler template to start Mapbender projects.

Find the GitHub Repository here: https://github.com/mapbender/mapbender-starter

7.1.6 External Repositories

You find more code connected to Mapbender at GitHub, which is not part of the main project. Other providers can offer Bundles for Mapbender like the DesktopIntegrationBundle which is provided by WhereGroup and sponsored by customers.

WhereGroup offers Bundles for Mapbender at: https://github.com/WhereGroup

7.2 Directory structure in Mapbender

7.2.1 application

Only in *Git-based installations*, the *application* directory contains the default Mapbender application. Some important subdirectories and files are:

- the *config* directory,
- the application kernel (*src/Kernel.php*) as entry point to the Symfony application,
- the Autoloading (vendor/autoload.php), auto-generated by Composer,
- the command line applications for maintaining and management tasks (bin/console, bin/phpunit) and
- .env and .env.local: Global configuration files, e.g. for database urls and smtp server connection.

bin

Here you find some libraries.

config

Basic configuration files of Mapbender are placed in the *config/* directory and the *config/packages* directory. These files are of particular importance:

- doctrine.yaml
- parameters.yaml

config/applications

The directory *config/applications* contains all applications that are defined in a YAML file. Find more information in *YAML Configuration (Configuration and Application files)*.

mapbender

- Directory of the Mapbender submodule. Provides the Mapbender-specific bundles and the Mapbender code.
- Directory for application resources (Resources/)

mapbender/..../translations

The translations are stored in YAML files. Every language needs a YAML-file, like *messages.fr.yaml* for the French translation of Mapbender.

• Directory path: ../mapbender/src/Mapbender/CoreBundle/Resources/translations/

public

This directory has to be published by the webserver. The alias has to refer to this directory.

It controls:

- *index.php*: The FrontendController (PHP script which can be called). Uses the productive or development mode depending on the definition of the APP_ENV variable, see *.env or .env.local file*.
- *index_dev.php*: Always uses the dev environment. Per default, access is only allowed from localhost. Find out more about giving access to other IP addresses in *Production and Development environment and Caching*.
- *public/* also contains the static resources like css, js, favicon etc.

public/bundles

- Is the storage for the static resources of the single bundles.
- The following command copies the resources from the bundles to the folder:

bin/console assets:install --symlink --relative public

Note: If you use Windows, you cannot create symbolic links and therefore have to run the command php.exe bin/console assets:install public to copy the files to the public directory after every change in JavaScript-, css-, twig- or image files.

SLC

Directory for application specific code and resources.

• The application kernel (*src/Kernel.php*) is called by the FrontendControllers and controls the whole application.

var

This directory contains:

- the caches (var/cache/dev and var/cache/prod),
- the logs (var/log),
- Sqlite-databases (*var/db/*).

vendor

Directory for external libraries (loaded by Composer) are placed here. Resources are used by Symfony using Autoloading:

• Autoloading: *autoload.php*

7.3 Concepts

This chapter will introduce you to the main concepts of Mapbender. After reading you should have an understanding of the parts Mapbender is made of and how they interact.

7.3.1 Application

The application is a single Mapbender configuration which is usually used as an interactive web map. It's what was called a GUI in Mapbender 2.

Every application consists of several components:

- Element
- Layersets
- Application Template

7.3.2 Element

Elements are the building blocks of every application. Each element provides some functionality and can interact with other elements. The map element is probably the element you face most of the time as it provides all map viewing capabilities.

Each element consists of four parts itself:

- PHP class describes the element with it's capabilities and also can provide an Ajax callback point, so that the client side widget (see below) can execute database queries and display the result for example.
- JavaScript widget this is the client side part of an element. It's everything you do and interact with on your screen. Using Ajax, it can call it's server-side counterpart to do things like database queries.
- Template HTML the element is using. In the most basic version, this would just be a DIV, but it can be as complex as is needed.
- CSS of course, most elements want some style, so they may provide their own.

7.3.3 Application Template

Each application is an HTML page, and the application template renders the basic layout of that page. Each application can have a different template as needed. Think of HTML templates specialised for mobile viewing.

7.3.4 Frontend

The frontend is basically the application view of your Mapbender installation. This includes the application list and each application view. It's what your users will interact with.

7.3.5 Backend

The *Backend* is where you configure your Mapbender installation. It's called the manager and allows your admins to manage users, groups and roles, services, applications and elements.

7.4 Translation in Mapbender

Mapbender uses the translator service which is a Symfony component. You get more information at the Symfony Translation Documentation.

In the code you use the function **trans** to translate a text into another language.

Example how the function **trans** can be used in a Twig template:

{% block title %}{{ application.title | trans }}{% endblock %}

ог

```
{% trans %}{{ application.title }}{% endtrans %}
```

Example for PHP:

```
echo $translator->trans('Hello World');
```

7.4.1 yaml-files for translations

The translations can be stored in different formats. We use yaml-format for Mapbender.

We use place holder for every text e.g. **mb.core.featureinfo.popup.btn.ok**. Like this you can define different translations for the same word which occurs in different modules.

We translate the place holder to different languages. English is the default language that we provide. It is also defined as the fallback language in the parameters.yaml file. The fallback language will be used if you define a language in parameters.yaml that does not exist.

This is how a translation file messages.de.yaml for German translation could look like.

```
mb:
  соге:
    featureinfo:
      еггог:
        nolayer: 'Informationsebene existiert nicht.'
        unknownoption: 'Unbekannte Option %key% für %namespace%.%widgetname%.'
        noresult: 'kein Ergebnis'
      popup:
        btn:
          ok: Schließen
      class:
        title: Information
        description: Information
      tag:
        featureinfo: Information
        feature: Objekt
        info: Info
        dialog: Dialog
    aboutdialog:
      content:
        versionprefix: Version
        learnmore: 'Lernen Sie Mapbender kennen '
        linktitle: 'Besuchen Sie die offizielle Mapbender Webseite.'
        website: '- zur Webseite'
        . . . . .
```

Notice: Each time you create a new translation resource you have to clear your cache.

bin/console cache:clear

7.4.2 How can you activate translation?

Mapbender is automatically adjusted to your browser's language. Moreover, you can set fallback language options in the configuration file *parameters.yaml*. If a translation from your browser's default language is not translated in Mapbender yet, it will fall back to the predefined language instead. We recommend to set English and/or German as fallback options.

fallback_locale: en locale: en

Check whether translations (yaml-files) for your language exist

- mapbender/src/Mapbender/CoreBundle/Resources/translations/
- mapbender/src/Mapbender/ManagerBundle/Resources/translations/
- mapbender/src/Mapbender/PrintBundle/Resources/translations/
- mapbender/src/Mapbender/WmcBundle/Resources/translations/
- mapbender/src/Mapbender/WmsBundle/Resources/translations/
- fom/src/FOM/CoreBundle/Resources/translations/
- fom/src/FOM/ManagerBundle/Resources/translations/
- fom/src/FOM/UserBundle/Resources/translations/
- ...

7.4.3 Create yaml-files for your language

If your language is not translated yet, it is easy to add a new language.

- Check the translation directories and create a new file by copying the English locale (messages.en.yaml)
- translate
- set locale in your parameters.yaml to the new language
- clear your cache
- adjust your browser language to the translated language Mapbender will be translated automatically.
- if everything is fine with your new language, give the files to the Mapbender community best would be a pull request on GitHub in the Mapbender repository.

7.4.4 Naming conventions and locations

Symfony looks for translation files in the following directories in the following order:

- the <kernel root directory>/Resources/translations
- the <kernel root directory>/Resources/<bundle name>/translations
- Resources/translations/ directory of the bundle.

Bundle translations can overwrite translations of the other directories.

Naming

The naming convention is **domain.locale.loader**.

- domain we use the default domain messages
- locale locale that the translations is made for (e.g. de, de_DE);
- loader defines the loader to load and parse the file. We use YAML.

7.4.5 Share your translations with the Mapbender community!

Supporting more and more languages would be great for Mapbender. The Mapbender project would be happy if you could share your translations with the community.

This is what you have to do:

- Option 1: send the new yaml-files for your language to the Mapbender developer (mapbender@osgeo.org) or
- Option 2: create a pull request on GitHub.

We prefer option 2.

How to translate and make a pull request

Repositories

- https://github.com/mapbender/mapbender/
- https://github.com/mapbender/mapbender-digitizer/
- https://github.com/mapbender/fom
- https://github.com/mapbender/data-manager/
- https://github.com/mapbender/data-source
- https://github.com/mapbender/map-tools/

Since Git is a distributed versioning system, it is very convenient for each developer/contributor to have a personal public copy of the "official" repository (also known as fork).

Web hosting services like GitLab or GitHub provide this option if you visit the main code repository and press the button "Fork". This way the developer can make changes to a personal isolated repository. Then one can ask the rest of the developers to review the code and merge accordingly through a "pull request".

Github - editing on GitHub

- you can edit files directly on GitHub.
- navigate to the file,
- edit the file,
- save changes and create a new branch for this commit and start a pull request.

git - working on the command line

On Linux systems get the source code locally using:

```
git clone https://github.com/your_id/mapbender
```

In order to be able to get and send changes to your public repository, you need to link your local copy to your public copy. This is done automatically for you when you "git clone". The repository that you cloned from has the alias "origin".

In order to be able to get changes that others do to the main repository, you need to manually link to that using:

git remote add upstream https://github.com/mapbender/mapbender

On MS Windows systems, install TortoiseGit, which extends Windows Explorer to include git commands.

1. The first thing you should do when you install Git is to set your user name and e-mail address.

```
git config --global user.name "John Doe"
git config --global user.email johndoe@example.com
```

cd mapbender

2. Pull any updates from upstream project (master is the equivalent of subversion trunk)

git pull upstream master

optionally check to see what has changed.

git diff messages.de.yaml

3. add the changes into stage area

git add messages.de.yaml

4. commit changes locally

git commit -m "changed translation"

5. send the changes to your public repository

git push origin master

At this point you can let others know that you have some changes that you want to merge, so you can use the button "Pull Request" on GitLab or GitHub. Or you can continue until you feel ready to share your changes :)

6. Last step: pull request

In order to merge your work with the main repository, you have to make a pull request.

You can do it by logging in your github account and go to the branch you changed. Click on the New pull request green button. The changes you made previously while appear.

You can review and comment your request before submitting. To submit, click on the Create pull request green button. Then, you're done ! Good job !

More information about Github pull request here: https://docs.github.com/en/pull-requests/ collaborating-with-pull-requests/proposing-changes-to-your-work-with-pull-requests/ about-pull-requests

Working with files:

to add a file

cd <dir>

create a file

git	add <file></file>
git	commit -m "commit message"
git	push origin master
CHAPTER

EIGHT

DEVELOPMENT

8.1 Introduction

This book is targeted at Mapbender developers and will cover useful topics not needed by administrators or users of Mapbender installations.

8.1.1 Things to consider

Warning: The development section of the documentation is partly deprecated, please read with caution. An updated technical documentation for developers is integrated into the Mapbender source code. It can be read directly on GitHub.

There are a couple of things you should be familiar with in order to contribute to Mapbender:

- Object-Orientated PHP: We're using PHP which offers full object orientation.
- Symfony: This is what we build upon. So read The Book to learn more about Symfony.
- JavaScript: We use jQuery a lot and especially the jQuery UI widget factory. These are essential to understand to write maintainable JavaScript code.

8.1.2 Installation

The installation procedure from Git is described under Git-based installation.

8.1.3 Modules and bundles

Please refer to the respective sections in the *CONTRIBUTING.md* guide to understand what modules and what bundles are, and how the latter can be created.

8.1.4 Twig

Symfony follows the template approach and we use this in Mapbender. Symfony uses a templating engine to generate HTML, CSS or other content. A template is a text file that can generate any text based format like HTML, XML. It is used to express presentation and not programm logic. You can use them to create a layout. You can create a base layout and then overwrite or append any of your layout blocks with individual templates. Read more about Templates in Mapbender at *How to create your own Template?* or in the Contributing Guide and find a good introduction about Twig in the Symfony Template documentation.

8.1.5 Overriding JavaScript and CSS/Sass Resources

Using the ApplicationAssetService class, JavaScript and CSS/Sass resources can be manually overridden:

To do this, use mapbender.application_asset.service within a class, e.g., in the *boot* method of your bundle file with \$this->container->get('mapbender.application_asset.service'). Alternatively, you can achieve this behavior in any PHP file with <argument type="service" id="mapbender.application_asset. service" />. Make sure to use a file that gets called, such as the template.

Then, call ApplicationAssetService::registerAssetOverride or ApplicationAssetService::registerAssetOverrides to mark assets for replacement. Below you will find an example that utilizes custom resources for the **Button** class:

```
class MyBundle extends Bundle
{
   [...]
  public function boot(): void
   {
     parent::boot();
     $assetService = $this->container->get('mapbender.application_asset.service');
      $assetService->registerAssetOverride('@MapbenderCoreBundle/Resources/public/sass/element/button.

→scss', '@MyBundle/Resources/public/element/my button.scss');

      $assetService->registerAssetOverrides([
            '@MapbenderCoreBundle/Resources/public/sass/element/button.scss' => '@MyBundle/Resources/
→public/sass/element/my_button.scss',
            '@MapbenderCoreBundle/Resources/public/js/element/button.js' => '@MyBundle/Resources/public/
→js/element/my_button.js',
     ]);
   }
}
```

Hint: It is also possible to override a resource in the parameters.yaml file.

8.1.6 Getting Help

Technical documentation

• Mapbender

Malinglists

• Mapbender-Developer and -User mailinglist

Libraries and frameworks

- Symfony framework
- Composer documentation
- General GitHub documentation
- GitHub pull request documentation

8.1.7 **Topics**

Controllers

Warning: The development section of the documentation is partly deprecated, please read with caution. An updated technical documentation for developers is integrated into the Mapbender source code. It can be read directly on GitHub.

This pages gives a quick overview of the controllers used in a Mapbender application.

The Front Controller - Using Routes

In Symfony, each HTTP request goes through the front end controller which determines the controller function to pass it to.

The mapping from request path to controller function is basically done in the configuration, where the routing.yaml defines these mappings - called routes - or imports their definitions from bundles (or other files).

To get an overview off all defined routes by using the console command.

cd mapbender/application bin/console router:debug	
[router] Current routes	
Name Metho	d Pattern
_assetic_30d3bc4 ANY	/css/30d3bc4.css
_assetic_30d3bc4_0 ANY	/css/30d3bc4_part_1_base_1.css
_wdt ANY	/_wdt/{token}
_profiler_search ANY	/_profiler/search
_profiler_purge ANY	/_profiler/purge
_profiler_import ANY	/_profiler/import
_profiler_export ANY	/_profiler/export/{token}.txt
_profiler_search_results ANY	/_profiler/{token}/search/results
_profiler ANY	/_profiler/{token}

(continues on next page)

_configurator_home	ANY	/_configurator/
_configurator_step	ANY	/_configurator/step/{index}
_configurator_final	ANY	/_configurator/final
<pre>mapbender_manager_layer_index</pre>	GET	/manager/layers/{page}
<pre>mapbender_manager_group_index</pre>	GET	/manager/group/{page}
<pre>mapbender_manager_repository_index</pre>	GET	/manager/repository/{page}
<pre>mapbender_manager_application_index2</pre>	GET	/manager/application
<pre>mapbender_manager_application_index</pre>	GET	<pre>/manager/applications/{page}</pre>
mapbender_manager_application_new	GET	/manager/application/new
mapbender_manager_application_create	POST	/manager/application
mapbender_manager_application_view	ANY	/manager/application/{id}
[and so on]		

The command lists all routes with their names, allowed methods and URL pattern. To get more information about a particular route, give it's name to the command:

```
bin/console router:debug mapbender_core_user_login
[router] Route "mapbender_core_user_login"
Name
             mapbender_core_user_login
Pattern
             /user/login
Class
             Symfony\Component\Routing\CompiledRoute
             _controller: Mapbender\CoreBundle\Controller\UserController::loginAction
Defaults
Requirements
Options
             compiler_class: Symfony\Component\Routing\RouteCompiler
Regex
             #^
                /user/login
            $#x
```

To learn more about routing, read the Symfony Book.

Defining routes using annotations

In Mapbender we use a decentralized route definitions: Instead of writing each and every route in the routing.yaml, we import their definition from the controller classes in the activated bundles. This has the advantage of having the definition with the controller function. This should usually be fine and can be - if need arises - easily overwritten by adapting the routing.yaml. Using the Symfony with the SE bundles like Mapbender does, routes can therefore be written using annotation comments for each controller function. You can read about the annotation syntax over at the Symfony documentation.

(continued from previous page)

Mapbender Controllers

A Mapbender installation uses a particular set of controller classes and functions. This chapter will give a short list of these, so you can inspect them more easily.

The Frontend

The frontend is basically "the application" (or GUI as it has been called in Mapbender 2 - and even there this term was incorrect). Each application is routed to the ApplicationController class of the CoreBundle:

/application/{slug} => Mapbender\CoreBundle\Controller\ApplicationController->applicationAction(\$slug)

Elements of an application can provide Ajax endpoints for their client side widgets. These are routed as follows:

```
/application/{slug}/element/{id}/{action} => Mapbender\CoreBundle\Controller\ApplicationController->
→elementAction($slug, $id, $action)
```

Note: This controller calls the **httpAction** method if the element class and passes the \$action parameter and returns the response given by that function. So for the real magic for element Ajax behaviour take a look at the httpAction method of the elements.

The Backend

The *Backend* is handled by the ManagerBundle, which provides (will provide) a consistent backend for managing all aspects of a Mapbender application: applications, layers, elements, users, settings.

For each section an own controller class exists within this bundle:

- ApplicationController Manage applications
- GroupController Manage user groups
- LayerController Manage layers
- RepositoryController Manage the layer repository
- SettingsController Manage common settings
- UserController Manage users
- plus an ManagerController which provides some common functionality for the other controllers.

Each of the these controllers (right now work is going on within the ApplicationController) is a good example of what we think of as good kinda RESTful URLs.

Understanding Elements

Warning: The development section of the documentation is partly deprecated, please read with caution. An updated technical documentation for developers is integrated into the Mapbender source code. It can be read directly on GitHub.

Parts of an Elements

PHP Class

TODO

Twig Template

Every Element must have an HTML element it is represented by. In the most basic case, this can be a simple DIV element, but this can be complex as needed.

For HTML generation, Mapbender uses Twig. A minimal twig template for an element would like this:

<div id="{{ id }}" class="mb-element mb-element-myclass"></div>

As you can see you need to set the id (generated by Mapbender) as well as the general mb-element class and a class specifically for your element.

JavaScript Widgets

Element widgets are build using the jQuery UI widget factory. This ensures a common pattern for widget development and offers

- default options.
- constructors and (optional) destructors.
- private and public methods.

The basic skeleton looks like this:

```
(function($) {
// This is the widget factory. It will create an widget class "mbMyClass" in the jQuery object as well
→as an
// "mbMyClass" object in the "mapbender" namespace in the jQuery object (they are used differently). Be
⇔suгe
// to use the "mb" prefix for your widget name as not to overwrite existing jQuery functions.
$.widget('mapbender.mbMyClass', {
   // This sets up the default options which can be overriden in the Mapbender configuration.
    // This will be moved into the PHP class at a later point.
    // The final options object can be accessed as "this.options".
   options: {
        foo:
                'bar',
        answer: 42
   },
   // This attribute is private for your widget.
   var1: null,
   // Constructor, gets called on widget initialization.
   _create: function() {
        // Do everything needed for set up here, for example event handling
        this.element.bind('mbmyclassmagicdone', $.proxy(this._onMagicDone, this));
        this.element.bind('click', $.proxy(this._clickCallback, this));
   },
    // Destructore, here set to the jQuery empty function
```

(continues on next page)

(continued from previous page)

```
destroy: $.noop,
    // Public function, callable like "$('#element-13').mbMyClass('methodA', parameterA, parameterB)"
   methodA: function(parameterA, parameterB) {
        this._methodB(parameterA);
    },
   // Private function, only callable from within this widget
    _methodB: function(parameterA) {
        // The triggered signal will be named "mbmyclassmagicdone" (all lowercase)
        this._trigger('magicdone');
   },
    _onMagicDone: function() {
        alert("Oh, magic!");
   },
    _clickCallback: function(event) {
        var target = $(event.target);
        var id = target.attr('id');
        // ...
    }
});
})(jQuery);
```

For event handling, jQuery.proxy is your friend to ensure that the callback is guaranteed to be executed in the right context:

```
// ...
this.element.click($.proxy(this._clickCallback, this));
// ...
```

This way, "this" inside the clickCallback method is the this given as the second parameter here (usually the widget instance) and not the HTML element which triggered the event. To access the HTML event, use the target property of the event passed as the argument to the clickCallback method.

Element to Element communication

There's an active and an passive way to communicate with another widget. The first - active - way is to call a public method of the other widget. For that you need to select the widget's HTML element with jQuery and call the method like this:

var otherElement = \$('#element-13').mbMyClass('methodA', parameterA, parameterB);

This is standard jQuery UI stuff and pretty much self-explanatory. The more tricky question is how do you know the other's HTML element? As you can see, using the id to select the element is preferred, but these ids are generated on the fly by Mapbender when the application is started, so you can't assume that the id is the always the same. Luckily you can pass a Element id in the configuration as the target options for an Element. This will be replaced with the run-time id of that target Elements' HTML element for you, so that in your widget code you can access the right id as "this.options.target".

\$('#' + this.options.target).mbMyClass('methodA', parameterA, parameterB);

The passive way for communication is to subscribe to events of another target. You also need to know the HTML element, but you can now listen for the other widget to call your widget. This is done using standard jQuery events. Well, almost standard jQuery events:

If you use the "_trigger" method provided by the jQuery UI widget factory

How to create your own Element?

Warning: The development section of the documentation is partly deprecated, please read with caution. An updated technical documentation for developers is integrated into the Mapbender source code. It can be read directly on GitHub.

Mapbender offers an bin/console command to create different elements:

- general elements
- buttons
- elements for map-click events
- elements for map-box events

Hint: The new generated element contains only a skeleton and has to be modified after generation.

The following example show the generation and modification of a map-click element.

The steps to create your own Element

There are some steps you have to follow on the way to your own element.

- create your own bundle
- create an element via bin/console
- edit your new element for your needs
- add the new element to the function getElements() to make it available from the Backend

Use bin/console to generate your own bundle

Find out more about the command with help:

bin/console generate:bundle --help

bin/console generate:bundle --namespace=Workshop/DemoBundle --dir=src

You have to answer some questions before the element will be created:

```
Bundle name [WorkshopDemoBundle]: WorkshopDemoBundle
Determine the format to use for the generated configuration.
Configuration format (yml, xml, php, or annotation): annotation
To help you get started faster, the command can generate some
code snippets for you.
Do you want to generate the whole directory structure [no]? yes
Summary before generation
You are going to generate a "Workshop\DemoBundle\WorkshopDemoBundle" bundle
in "src/" using the "annotation" format.
Do you confirm generation [yes]? yes
Confirm automatic update of the Routing [yes]? yes
```

After this steps you new bundle is available at src. The bundle is already registered in the file Kernel.php. In the file routing.yaml you will find a new entry for the bundle.

Edit your new element for your needs

Change the title and description in the php file

You will find several functions in the php file. Change the return value of the functions *getClassTitle()* and *getClassDescription()*.

```
public static function getClassTitle() {
    return "MapKlick";
}
```

```
public static function getClassDescription() {
    return "Generates an Url with the the mapklick coordinates added";
}
```

Register the new Element

You can register an element by adding it to the function *getElements()* in the file src/Workshop/DemoBundle/WorkshopDemoBundle.php. After creation of the bundle this function does not exist. You also have to refer to the MapbenderBundle and define that your extends the MapbenderBundle.

This will make the element available in the *Backend* when you configure your application.

<?php

namespace Workshop\DemoBundle;

use Symfony\Component\HttpKernel\Bundle\Bundle; use Mapbender\CoreBundle\Component\MapbenderBundle;

(continues on next page)

(continued from previous page)

```
class WorkshopDemoBundle extends MapbenderBundle
{
    public function getElements()
    {
        return array(
            'Workshop\DemoBundle\Element\MapKlick'
        );
    }
}
```

Add the new element to an application

Create a new application and add your element to the new application. Note that the configuration for your generated element is done in YAML syntax. If you want to use the map-element as target you have to find out the id of the map-element (e.g. via inspector tool).

Change the action on Click event

When you generated a map-click element you get an event on click and an action. The action can be modified. Have a look in the JQuery widget file (mapbender/src/Workshop/DemoBundle/public/mapbender.element.mapklick.js).

You will find the function _*mapClickHandler()* that determines the coordinates from the click event and passes them to the function _*mapClickWorker()*. The new generated element will show the coordinates of the click event in an alert box.

You can modify the action of the function _mapClickWorker().

Default definition of _mapClickWorker()

```
_mapClickWorker: function(coordinates) {
    alert('You clicked: ' +
        coordinates.pixel.x + ' x ' + coordinates.pixel.y +
        ' (Pixel), which equals ' +
        coordinates.world.x + ' x ' + coordinates.world.y +
        ' (World).');
}
```

modified _mapClickWorker() opens OpenStreetMap

Alternatively you could open a new window with an URL and add the coordinates as parameters. You can open OpenStreetMap and center to the coordinates of the click event.

https://www.openstreetmap.org/export#map=15/50.7311/7.0985

CHAPTER

NINE

VERSION HISTORY

German version of this document.

Note: This version history is no longer maintained. Please head over to GitHub to see the latest Mapbender Changelog and Version Milestones.

9.1 Version 3.2.9

Release date: 28.01.2022

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v329

9.2 Version 3.2.8

Release date: 02.11.2021

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v328

9.3 Version 3.2.7

Release date: 07.09.2021

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v327

9.4 Version 3.2.6

Release date: 09.08.2021

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v326

9.5 Version 3.2.5

Release date: 08.06.2021

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v325

9.6 Version 3.2.4

Release date: 04.03.2021

Improvements and bugfixes:

https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v324

9.7 Version 3.2.3

Release date: 21.12.2020

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v323

9.8 Version 3.2.2

Release date: 02.11.2020

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v322

9.9 Version 3.2.1

Release date: 06.08.2020

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v321

9.10 Version 3.2.0

Release date: 29.07.2020

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v320

9.11 Version 3.0.8.6

Release date: 15.09.2020

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3086

9.12 Version 3.0.8.5

Release date: 05.02.2020

Improvements and bugfixes:

https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3085

9.13 Version 3.0.8.4

Release date: 04.09.2019

Improvements and bugfixes:

https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3084

9.14 Version 3.0.8.3

Release date: 05.07.2019

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3083

9.15 Version 3.0.8.2.1

Release date: 05.07.2019

Improvements and bugfixes:

https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v30821

9.16 Version 3.0.8.2

Release date: 03.07.2019

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3082

9.17 Version 3.0.8.1

Release date: 14.05.2019

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3081

9.18 Version 3.0.8

Release date: 12.04.2019

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v308

Upgrading

https://github.com/mapbender/mapbender/blob/master/UPGRADING.md#308

9.19 Version 3.0.7.7

Release date: 07.11.2018

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3077

9.20 Version 3.0.7.6

Release date: 18.10.2018

Improvements and bugfixes:

• https://github.com/mapbender/mapbender-starter/blob/master/CHANGELOG.md#v3076

9.21 Version 3.0.7.5

Release date: 26.09.2018

Improvements and bugfixes:

- Find the description of the fixes in the repository links
- Update Mapbender-Starter v3.0.7.5
- Update Mapbender to v3.0.7.5
- Update Owsproxy to v3.0.6.4, includes Owsproxy dependencies
- Update mapbender/vis-ui.js to 0.0.72
- Update mapbender/data-source to 0.1.8
- Update mapbender/digitizer to 1.1.66
- Update bundled Composer to 1.6.5
- Misc ComposerBootstrap cleanups

9.22 Version 3.0.7.4

Release date: 29.08.2018

Improvements and bugfixes:

- [Security] In some development environment a XSS error can occur with the assets. This error was only observed on some environments with specific debug PHP settings (error_reporting z.B. E_ALL).
- Revert the column type of the keyword-column to "varchar" to avoid incompatibilities with Oracle. Very long keywords are truncated back to 255 characters (#1000).
- Some JavaScript fixes that leads to problems with defunct Internet Explorer 11 (#990).
- Empty layer-names are not requested again in FeatureInfo (PR #1010).
- Doctrine optimizations to store layer-order settings in PostgreSQL.
- Reggression fix in WMSLoader and image format / info format settings.
- Fix on Delete Cascade SQL statements with PostgreSQL, when deleting a WMS source.
- Fix in translations when only a placeholder was set. These fall back now to the fallback translation (per default: english).
- Update OSGeo Logo (PR #861)

Notes for the update:

Please call again the **app/console doctrine:schema:update** command to set back the keyword-table and column to varchar.

app/console doctrine:schema:update

If this statement fails, for example with the PostgreSQL error SQLSTATE[22001]: String data, right truncated: and 7 ERROR: Value too long for type character varying(255), you probably have a keyword-entry in the table mb_core_keyword, that exceeds the length of 255 characters. You can find out this entry with the following SQL-statement:

```
SELECT x, id, length(x) FROM (
    select value, id from mb_core_keyword
) AS t(x) order by length desc;
```

9.23 Version 3.0.7.3

Release date: 13.07.2018

General:

- Change of the Mapbender logo and the name: Mapbender3 is due to simplicity reasons renamed into Mapbender and we have change all texts in this documentation and the logos. Our URL were changed to http://mapbender.org some time ago.
- Mapbender requires at least PHP > 5.6 for running. We recommend PHP 7.

New functions:

- QGIS Server layer ordering, documented at layerset
- New element: *Coordinates Utility*
- Mouse-Over in SearchRouter
- GPS Button in POI
- Dynamic Loading of legend-images in the legend-element (PR #605, PR #606)
- Display of a cookie banner in applications. See *Cookie Banner*.

Changes:

- Die default applications are moved to the directory *(application)/app/config/applications*, each in its own file. This includes
 - the Mapbender Demo Map application
 - the Mapbender Demo Map basic application
 - the Mapbender mobile application

Additional YAML-applications can be placed there.

Improvements:

WMS Loader and WMS Services:

- Improvements in WMS Loader service compatibility, which logic now matches the backend
- Fix in the GetLegendGraphic request for a secured service via the tunnel
- Fixes and improvements for the URL-signing (#590)
- Many improvements in the WMS Backend
- Fix in instance-tunnel while requesting secured services
- Fix on accessing WMS services with undefined contact information.
- Various fixes to displaying and handling min / max scale definition from sublayers vs root layers
- Fix saving layer order on PostgreSQL
- Services loaded with WMS Loader and their metadata display. We cannot read the properties, but we don't throw an error anymore.

Design and CSS:

- Changed Opacity for zoombar and toolbar to get a unique button color
- Fix for creating an application and adding the screenshot

Print:

- Fix printing PNG8 maps if the image format was specified as "image/png; mode=8bit".
- Fix printing special font-sizes (especially at Windows with PHP 7.1)
- Fix in printing if PHP notices were switched on in php.ini and the yStartPosition was missing (#555)

FOM:

- Improvements in FOM: Wrong Type Definition in ACL Provider Constructor #641
- Improvements in FOM at SSPI

Translations:

- Improvements in the translations. Thanks to the Code-Sprint of the FOSS4G!
- Changes in translations from XLIF to YAML in the modules FOM and OWSProxy

Miscellaneous:

- Per default the maximum feature count for GetFeatureInfo is now 1000.
- Fix in the scale-selector, which did not want to refresh itself
- Fix in the call of Mapbender with the POI parameter (#642)
- Fix in the legend-element for oversized legend-images (#640)
- Fix on adding new elements in the backend
- Fix foreign key violation error in PostgreSQL when deleting data source (PR#840).
- Add cookieconsent code for Mapbender
- Change default prefix for printouts to mapbender

Code-Improvements:

- Update to Symfony 2.8 (please see the PHP requirements)
- Introduction of the Doctrine Migrations framework
- Fix possible URL signing spoof with input URLs missing query parameters.
- Doctrine Param Coverter definitions (PR #645)
- WMSLayerSource: getAuthority (PR #542)
- DimensionsHandler (#610). This will be published in the forthcoming versions
- Adding elements in backend can fail with "Warning: usort(): Array was modified ..." (#586)
- Element Template and AdminType Fixes (#743)
- Serialization of MetadataURL (#747)
- UnitTest and Pre-Conditions (#760)
- USort und array_multisort with a PHP-bug (#586)
- Fix strict SCSS warnings when compiling with ruby-sass
- Fix unbounded growth in "authority" on repeated export / reimport / cloning of applications

- Bypass (potentially very long) WmsLoader DTD / XSD validation of GetCapabilities document
- PHP 5.6 compatibility with Migrations

Documentation:

- New design of the documentation. We have changed the theme to the Sphinx RTD theme. The documentation is now easily readable on mobile devices. You can also print out specific pages.
- Restructuring of the documentation. The specific *Elements* are sectioned into:
 - Base elements
 - Search
 - Export / Print
 - Editing
 - WMC
 - Backend
 - FOM
 - Other
- Improved documentation for the elements:
 - Base source switcher
 - Button
 - Coordinates Display
 - HTML
 - Legend
 - Мар
 - Navigation Toolbar
 - Overview
 - Search Router
 - SRS Selector
- Improvements for the *PrintClient* and the new dynamic features on print-templates.
- Included the MS4W package for installation under *Installation on Windows*. Please take a look. And thank Jeff McKenna.

Notes for the update:

Please call the command **app/console doctrine:schema:update** for the Update to this version. The QGIS layer ordering needs a change in the Mapbender database. Also the 255 characters for WMS services require a change of the database.

app/console doctrine:schema:update

9.24 Version 3.0.7.2, 3.0.7.1 und 3.0.7.0

Due to tagging-errors of the code in Github these versions were never officially released. It's not a good idea to re-tag the code, so we continued with Version 3.0.7.3.

9.25 Version 3.0.6.3

Release date: 27.07.2017

Bugfixes:

- Regression: Fixed coordinate order at requests to a WMS 1.3.0. Coordinate reference systems with reversed axis-orientation are supported by map, print and export. (#529)
- Regression: Fixed ScaleHint for WMS services. Some WMS services that defined a Scale in their Capabilities couldn't be put into an application. (#584)

9.26 Version 3.0.6.2

Release date: 20.07.2017

Bugfixes:

- Search Router: Error with OpenLayers fixed (#543)
- Search Router: Auto Close after Click in mobile application (#548)
- Coordinate order (axis order) on requests to WMS 1.3.0 fixed (#529)
- Print: Rendering of points and labels on high-resolution Print (#573, #574, #492)
- Saving of WMC in WMC editor dialog (#577)
- ScaleHint for sub-layers of 1:1 fixed (#565)
- Widen the Title-Columns on Layerset-Instances (#559)
- Command to update the image-path in existing map-elements (#530)
- Translation of Print-button in FeatureInfo dialog (#552)
- Change of default-value of "immediate" in measure-tools (#538)
- SRS: Update of definitions (#550, #562) and update of YAML standard applications (#561)
- Update documentation for handling of translations.

Additional update steps:

(1) Update of EPSG-Codes

Execute again the command app/console doctrine:fixtures:load --fixtures=mapbender/src/ Mapbender/CoreBundle/DataFixtures/ORM/Epsg/ --append. Two new coordinate-systems are added to the Mapbender database-table mb_core_srs: EPSG:4839|ETRS89/LCC Germany (N-E) and EPSG:5243|ETRS89 /LCC Germany (E-N)).

(2) Update of parameters im Map-Control

Execute the command app/console mapbender:upgrade:database, to update the OL-imagePath Parameter from bundles/mapbendercore/mapquery/lib/openlayers/img to components/mapquery/lib/openlayers/ img. This is necessary if you use the POI-Elements or call Mapbender with the poi-parameter and see no bubble-icon for the poi. Example: https://demo.mapbender.org/application/mapbender_user? poi{[]point{]}=366164%2C5623183&poi{[]scale{]}=25000&poi{[]label{]}=Please+take+a+look+at+this+POI%3A

9.27 Version 3.0.6.1

Release date: 24.05.2017

Bugfixes:

- Print map showed wrong scale in map-display.
- Specific WMS could not be printed due to HTTP response image/png; charset-iso....
- Backend: FOM dialogues with many entries made checkboxes unusable.
- config.php back in mapbender-starter.
- Update bin/composer build command for building Mapbender.
- Style-Fix for administrations-dialog of Basesource-switcher.
- Add WmcEditor Default Parameters for width and height.
- Update landing-page of this documentation.
- Some minor styling changes in backend.
- Some cleanup.

9.28 Version 3.0.6.0

Release date: 05.05.2017

Architecture:

- System Requirement PHP: 5.5.4 or higher.
- Support of PHP 7.
- Mapbender, FOM and OWSProxy excluded into Modules. They are now bind in composer.json
- Documentation is part of the composer.
- Adjustments of the ElementGenerator
- Determining of user-roles
- Composer entries with https
- Adjustments of Controllers and Bundles.
- Doctrine generate commands are marked deprecated
- Doctrine assets:dump command is marked deprecated
- Update of the JOII library
- Introduction of symblinks to the different binaries in the bin directory of mapbender-starter

- Composer shipped in application/bin directory
- Check in the Composer-installation, if the SASS Compiler Binaries are executable. If not, they are set executable.
- New Composer commands for documentation: Generate API documentation only: bin/composer gen-api-docs
- New Composer commands for documentation: Generate User-documentation only: bin/composer gen-user-docs
- Use of own forks of open-sans, joii, compass-mixins and codemirror libraries.

Bugfixes und Features:

- Measuring shows the coordinates directly, by moving the mouse the calculated lengths of the segment are displayed live.
- New measuring results are shown on Top. The current result is visible at first place and you don't need to scroll.
- The login-dialog (registration, forgotten password) is optimized for mobile devices to achieve a better workflow to secured mobile applications.
- New added layerset instances are now per default not marked as base-source.
- The Copyright element popup can be defined with a height and a width.
- Deleting a layerset led in some cases to a corrupt map element and a wrong layertree.
- Adjustments and Simplification of the general style of the FullScreenTemplate
- Introduction of the check of the CSS statements in a application
- Fix in the delay when switching layers.
- Fix in GetMap request if the layer order was changed manually in the TOC.
- Fix for WMS support 1.3.0
- Fix for secured WMS services on GetMap, GetFeatureInfo, Print, Export and Legend.
- Fix for secured WMS services where the username or password included a hash-character.
- Fixes for the WMS parameter Exception Format for the GetMap and GetFeatureInfo Request (Github-Issue 400)
- Fixes of Layer-Styles for GetMap und GetFeatureInfo request
- Default Tile Size for the Map set to 512 (was 256)
- WMS Keyword limit (was: 255 characters) is changed. The column-type is now "text". The command app/console doctrine:schema:update is necessary to update the Mapbender database of a previous version.
- Fix when importing YAML based applications and creating duplicate WMS data-sources.
- Fix on minimal and maximal scale hint on WMS services.
- Print: Color can be set for variable texts.
- Print: Printout of the legend, if the service is built in with the proxy.
- Print: Services registered with PNG8 could not be printed or exported in some cases. The types image/png8 and image/png mode=24bit is not supported.
- Print: In some cases, the legend wasn't printed if OWSProxy was activated

- BaseSourceSwitcher: Duplicate request on WMS which was not visible and where the BaseSourceSwitcher was used as a menu.
- Unneccessary requests on specifc WMS configurations with scale.
- Saving of YML applications in application/app/config/applications: mapbender_mobile.yml, mapbender_user_basic.yml, mapbender_user.yml and adjustments in their referenced WMS Version
- Fixes in administration interface of the YAML editing after saving (Github-Issue 350)
- Fixes in POI-Coordinate: Transformation and SRS and the trailing digits after the comma.
- Fix of a XSS error in POI dialog
- Fix in POI dialog, if useMailto is set to false
- GPS: Error messages if no GPS signal and the dependency to Chrome-browser and https.
- GPS: Pan the map only on first position.
- User-Interface: Scrolling of a drop-down list in backend, for example the icons for the buttons, did also scroll the background.
- "Only valid" Checkbox on loading a WMS is now per default not activated anymore.
- Reformatted messages if the schemes of a WMS are not accessible when adding a WMS.
- The SearchRouter shows, if placed in the sidebar, the Search and Reset buttons.
- Internet Explorer Compatibility: Adjustments in the Zoombar..
- Internet Explorer Compatibility: Adjustments in the OverviewMap.
- MS Egde Compatibility: Trying to fix the Import Dialog (https://connect.microsoft.com/IE/feedback/ details/1574105/microsoft-edge-file-upload-bug-build-10240-rtm)
- Improvement of the performance on *some* Windows installations through WinCachePHP and PHP Opcache (for details see Installation under Windows)
- Change in System-Requirement for Windows: For PHP, the "Non-Thread-Safe" version is needed!
- Copying of applications through users who are not root (ACL Application: owner, Users: owner, ACLs: owner, Element: owner, Groups: owner, Service Source: owner, specific applications: owner)

FOM and Security:

- Show the users who have a access on an element in an application.
- Rework of the Secure Elements dialog.
- User with the role View for services are allowed to view the Metadata and to load the services into an application.

miscellaneous

- Design and presentation of the FeatureInfo dialog if shown as Accordion. Also if shown as "not from source".
- Drag of Popups in an application.
- WMC Editor: Adjustments in size. XSS fix.
- Fix of translations
- YAML based applications can adjust the sidebar: align (left/right), closed (true/false), width (px/em/%)
- Backend: Target field: Empty option of a Drop-Down field.

- Adjustments of WMS Scale, ScaleHint and Min/Max values when a Layerset-Instance is opened.
- Display of WMS Title in the metadata of the TOC, when the WMS was updated.
- Display of the application logo in the Configuration.
- Display Issues of Simple Search and Search Router.
- Fixes for error messages on a wrong configured Layerset-Instance.
- Print: Introduction of setasign/pdf instead of toooni/fpdf
- Print: Fix of error messages on a missing print-template
- Measuring of lines and polygons in WGS84 (EPSG:4326)
- Adjustments of display of the element ACL
- WMS Update: remove user/password from web-browser autocomplete
- Display of number of digits in coordinates-display.
- Adjustments and extending EPSG import
- fix default visibility for a layer and the scale
- remove of DataSource Monitor icon (comes in version "next")
- Administration: Movement on the tabs with the tab-key
- Improvement of the display of the configuration interface
- Display of Source-ID in applications
- Improvements of Caching Mechanisms
- Improvements of Export and Copy mechanism.
- Improvements for the creation of new elements.
- Remove the provide ext-ldap statement in Composer. The components are released from the core. We will build in the LDAP module in version 3.0.7.
- Restructuring of DataManager and DataSource since version 1.0.2 of data-manager.

Mobile template

- General improvements of the mobile template.
- Fix handle mobile template button click if target isn't defined
- Set mobile icon label font weight to normal
- Fix and improve mobile template button handling
- Fix register mobile application event handler "on moveend"

Digitizer

- Update Digitizer to version 1.1.
- Printing of Multipolygons.
- Objects don't appear in the printout if they are not displayed in the Digitizer.
- MinScale restriction added
- Objects with a line-width of 0 are now not shown anymore in the printout.
- Adjustments of the Close Button: "allowCancelButton" and "allowDeleteByCancelNewGeometry".

Form Generator:

• Adjustments: Add HTMLElement handling of service and DataStore configuration.

Dokumentation

- Introduction of the FAQ.
- Introduction of Contributing Guide for Mapbender-Starter and OWSProxy. Mapbender itself and FOM will follow. This is the main documentation for developers and contributors of Mapbender.
- The developer documentation will be maintained there and be transferred step-by-step from this user-documentation. So in the future this documentation here will be more for users and the developers have their documentation directly in the source code of the different modules.
- Better Layertree documentation

config.yml Anpassungen

DBAL-Parameter:

- default_connection: If more database entries are defined, this parameter
- persistent: Persistent connections to the database for performance reasons (Oracle)

mapbender-starter/application/app/config/applications/

Directory where YAML-based application definition are stored. As an example the well-known applications Mapbender-User, Mapbeder-User-Basic and Mapbender-Mobile are placed here.

app/console doctrine:schema:update

```
app/console doctrine:schema:update --dump-sql
ALTER TABLE mb_core_keyword ALTER value TYPE TEXT;
ALTER TABLE mb_core_keyword ALTER value DROP DEFAULT;
```

9.29 Version 3.0.5.3

Release date: 04.02.2016

Bugfixes:

Notable Modifications:

- Performance: The CSS, JavaScript and Translation files are now held in the Symfony Cache for the production mode. This can lead to better performance on slower machines. These cache is not used by the development-mode.
- The package eslider/sassc-binaries offers now a sassc Compiler for 32-bit Linux systems. This led to a wrong display on 32-bit Linux-Systems (http://lists.osgeo.org/pipermail/mapbender_users/ 2015-December/004768.html)

• Redlining: The contents of the Redlining element is visible and Redlining can now be used as a Dialog or an Element in the Sidepane. See also the documentation of the Redlining Element. The scroll bar for the Geometry-Types in the configuration dialog is now displayed correctly.

Users and security:

- Users can be switched active or inactive by an Administrator, who has at least the ACL-user-right "operator". This can be used for users, who have self-registered but not yet activated their account. See the documentation of user-management for details.
- The text, translations and styles for the Self-Register process and the Password Reset are improved. Also the Documentation is adjusted.

Print and export image:

- The Print module can now also be used in the Sidepane.
- Print legend: The size of the legend in the print-out was scaled down to improve the quality.
- Print-templates: The default print-templates have changed. The padding of the dynamic texts to their border and their justification were improved.
- Print: The Print configuration messed up mandatory (required: true) and optional fields (required: false), if they were used in combination. Optional fields were partly shown as mandatory (Github #380).
- In some cases Mapbender printed the legend of all WMS-layers, even if the layer was not set active (seen in Mapbender_Users WMS).
- Export Image: Transparency of tiled and non-tiled services is supported in Export Image.

Copy and import:

- Copying an application under SQLite and MySQL: There was en error that applications could not be copied if the database was SQLite or MySQL.
- Errors at the import of application as JSON on MySQL (elements lose their target) was fixed.

Individual Elements:

- **WMC** and thematic layertree: If a WMC is loaded and Keep Sources is set to "no", the thematic layers are now also removed from the layertree.
- WMS-URL parameter and legend: If a service was loaded with the wms_url parameter, the complete legend was shown. This behaviour is fixed.
 - Note: WMS services exists, which define a legend in the root-layer element. According to the WMS-specification, this legend will be inherited by sub-layers who itself haven't defined a legend (for example if they only contain the annotations). The effect is similar in MB3 but the cause is different, so that in these cases a change in the WMS capabilities is needed (define a static legend image for these layers).
- **Thematic Layer**: Fix in switching layers on and off which are in their own Layerset but not displayed as a thematic layer.
- **Coordinate display**: The coordinate-element display doesn't show "null" as prefix or separator anymore, although the field was defined as empty. The element has get a fixed with so that the layout in the footer region is more sable. The value can be changed (see the chapter CSS-customizing of the element).
- **SearchRouter**: The content of the result uses the whole space of the dialog and fits itself to changes of the size. In the sidebar the whole height is used. The search router can be configured with a width and a height.

- **ScaleSelector**: The width of the element can be customized with a CSS-Statement and is no more set to 155 pixel.
- If all layer in a **layerset-instance** are set to visible=off they were not visible in the layertree and the legend. This is fixed.
- Improvements in the styling of the **POI dialog** if "usemailto" is set to false.
- Layertree: Titles are now shown per default with a length of 40. The default value has been changed. You can set the parameter Titlemaxlength in the configuration dialog.
- **GPS**: Improvements in the GPS handling.

General changes:

- Changing the Base Data, the Layout, the Layerset, the CSS and the Security of an application does not change the tab anymore and doesn't jump back to the base data tab.
- General improvements of the Digitizer Code version 1.0. Version 1.1 is compatible with Mapbender 3.0.5.3.
- Github files: Small clean up actions in the Github repository to improve the automatic buildprocesses.
- Transparency of services: Services with a transparency refreshed with a poor effect, caused by the "transitionEffect" in OpenLayers. The effect was removed.
- Group filter: The security configuration dialog got improvements at the selection of Groups, if the Groups had the same name but a different suffix.
- TileSize Parameter in the map configuration was not set in some cases.
- Display of symbols in Internet Explorer 11 and MS Edge 25 (also an error in MS Edge 20).
- mapbender.yml: At the initial import of the mapbender.yml the values of GetFeatureInfo are now set to text/html. The mapbender.yml can now customized with Redlining.

Change of the Mapbender domains:

- We have switched the URL www.mapbender.org to the Mapbender3 page. In future, the Mapbender3 page is also available via www.mapbender.org and www.mapbender3.org. Mapbender2 is now available at www.mapbender2.org
 - http://www.mapbender.org: Mapbender3,
 - http://www.mapbender3.org: Mapbender3,
 - http://www.mapbender2.org: Mapbender2.

Known Issues:

- The Sketch Tool doesn't work correctly and will be built into the Redlining Tool.
- Share map doesn't work for Facebook, Twitter und Google+.

9.30 Version 3.0.5.2

Release Datum: 27.10.2015

Bugfixes:

- Copy applications: User-Rights and groups are copied. The user who copied the application becomes owner of the copied application.
- FOM: Changes in behaviour of wrong logins and user locking. It is only shown that the login failed, independent if the user exists or not.
- Fixed error message when creating a user with a too short password.
- Print: Fix of replace pattern.
- Print: Fix if a wrong configured WMS has special characters (%26) in the legend URL.
- Image export in Firefox.
- WMC Loader: Loading WMC and Behaviour of BaseSources.
- BaseSourceSwitcher: Tiles of a not visible service are not pre-fetched.
- BaseSourceSwitcher: If a group is defined, only one theme is switched on.
- SearchRouter: Fix of quotes for table-names.
- Copy applications: Fix of the search in the copied application.
- Simple Search: Catch the return key.
- FeatureInfo: Add WMS functionality and WMS Loader.
- Icon Polygon is visible in the toolbar of applications.
- Icons, which are not based on FontAwesome also work in the mobile application.
- Administration of the map element: The view of the configuration dialog in the backend starts on top.
- Administration data source: No form data auto-complete from the browser for username and password.
- Mobile application: Design in Firefox for Android.
- Update 3.0.4.x: FeatureInfo autoopen=true is kept.
- Doku: FOM UserBundle translation and additional information for failed user logins.
- Doku: URL parameter scale in map element.
- Doku: WMC Loader and KeepSources.

Changes in config.yml:

• The following changes are optional parameters for the behaviour of the login (see also the chapter in the FOM bundle for details):

fom_user:

```
# Allow to create user log table on the fly if the table doesn't exits.
# Default: true
auto_create_log_table: true
# Time between to check login tries
```

(continues on next page)

(continued from previous page)

login_check_log_time: "-5 minutes"

```
# Login attemps before delay starts
login_attempts_before_delay: 3
```

```
# Login delay after all attemps are failed
login_delay_after_fail: 2 # Seconds
```

9.31 Version 3.0.5.1

Release Datum: 26.08.2015

New functions: in the Map element and in the Print client:

- Map: OpenLayers TileSize: You can set the tile-size for the map. Default: 256x256.
- Map: Delay before Tiles: For WMS-T, for example with temporal parameters (in future)
- Print: Show coordinates in PDF print
- Print: get print scale depending on map-scale
- Print: print legend_default_behaviour
- Print: add print templates with the + symbol
- Print: user-defined logo and text

Bugfixes:

- Layertree: loading symbol and exclamation mark symbol.
- Layertree: zoom Symbol not for layers without a BBOX information
- WMS Reload: FeatureInfo
- WMS Reload: some WMS couldn't be reloaded.
- Export/Import of application and miscellaneous bugfixes
- WMC-Editor and WMC-Load fixes.
- WMC from a Mapbender 3.0.4.1 application
- Tile buffer and BBOX buffer fixes
- FeatureInfo: Fixes in design and when shown as an Accordion Panel
- FeatureInfo: Print
- Wrong Jquery-UI link in layerset instance
- Save Layerset and Save Layout leaves you on the page
- Classic Template: SCSS corrections
- Mobile Template: Bootstrap message hides close button
- Mobile Template: close SearchRouter window
- Mobile Template: Mozilla Firefox Fixes on layout
- Backend: Layerset Filter and +-Buttons doesn't hide everything anymore

- composer.json upgrade version of Digitizer to 1.0.*
- Documentation of the JS-UI Generator (Form-Generator): https://github.com/eSlider/vis-ui.js
- Restructured Installations-Dokumentation and some changes (php-pear, assets-Verzeichnis, init:acl, openssl).
- Better documentation of the Mapbender3 Templates
- Better documentation of the Quickstart

Known Issues:

- After copying an application from Mapbender 3.0.4.x you have to set the layerset in the map/overview element. Please save the map and overview element beforehand.
- Regional Template removed

9.32 Version 3.0.5.0

Release Date: 01.07.2015

For details have a look at: https://github.com/mapbender/mapbender-starter/blob/develop/ CHANGELOG.md

- WMS reload: WMS sources can now be reloaded if the structure has changed.
- **Digitizer:** The digitizer allows the editing of geometries and their attributes. Right now it needs access to the database where the editable tables are. The definition of the digitizer is done in YAML syntax. To provide an usable interface for the attributes, you can declare the form in your configuration file. The form supports different input fields (textboxes, checkboxes, date-pickers, and so on..), validation, tabs and it uses Bootstrap.
- **Print with legend:** The print element supports the print-out of the legend on a seperate page. This can be set with a checkbox.
- **Configurable layertree:** The layertree supports the usage of more than one layerset. You have to adjust the map element to define which layersets should be shown and the layertree element itself. The usage is documented on the Layertree page.
- Improved FeatureInfo dialog: You can set a) the width and height of the FeatureInfo dialog, b) if the dialog should show the original format of the WMS and c) if it should only open if a valid entry is found (otherwise a messagebox is displayed). See the documentation of the FeatureInfo Dialog.
- Mobile template: A new modern mobile template is provided.
- **SASS Compiler:** Architectual changes are made at the SASS compiler which leads to a more performant interface.
- Vendor Specific Parameters: A WMS layer instance supports the definition of Vendor Specific Parameters that are added to the WMS request. You can define hard coded values or the user or group information of the logged-in user. See the documentation of Vendor Specific Parameters for details.
- **Expanded functionality of HTML elements with a form-builder:** This approach is used in the Digitizer to provide the forms for attribute editing.
- New button colletion: The new buttons are based on a new font, the old buttons are available under the "FontAwesome" name.
- **Starting mapbender with URL parameters:** Mapbender3 can be started with URL parameters. See the documentation of URL parameters.

- New translations for Portuguese and Russian.
- Symfony updated to 2.3.30.

Changes in config.yml:

- Changes in a dbal connection:
 - logging: false: This options sets, that *all* SQL statements are not logged. Further information can be found here: http://www.loremipsum.at/blog/doctrine-2-sql-profiler-in-debugleiste/
 - **profiling: false**: This option handles the profiling of SQL statements. This option can be switched off in production environments.

If possible the options should be set this way, so that they are only active in debug mode:

| logging: | "%kernel.debug%" |
|------------|------------------|
| profiling: | "%kernel.debug%" |

Known Issues

• After copying an application from Mapbender 3.0.4.x you have to set the layerset in the map/overview element.

9.33 Version 3.0.4.1

Release Datum: 23-01-2015

For details have a look at: https://github.com/mapbender/mapbender-starter/blob/develop/ CHANGELOG.md

- option 'removelayer' added into layertree menu
- parameter 'layerRemove' removed from layertree configuration
- container accordion structure changed
- import / export from applications added (without acls)
- display layer metadata
- Frontend: Sidepane Accordeon Legend is displayed without horizontal Scrollbar
- Backend: WMS Instanz configuration contextmenu for layers shows wrong ID (only instance ID)
- Frontend: Legend displays WMS Information although the checkbox Show
- Frontend: Layertree contextmenu zoomlayer does not use the layer extent
- Backend: Add Source with user/password informations is added to field originUrl not to fields user and password
- app/console mapbender:generate:element fixed errors
- bug visiblelayers fixed
- WMS with authentication saves in table mb_wms_wmssource username and password
- no metadata for applications coming from mapbender.yml definition (no entry in context menu)
- copy an application via button on application fixed
- print template resize northarrow, overview added
- improved screenshot for application handling

• https://github.com/mapbender/mapbender/milestones/3.0.4.1

9.34 Version 3.0.4.0

release date: 12-09-2014

For details have a look at https://github.com/mapbender/mapbender-starter/blob/develop/ CHANGELOG.md

- Switched to MIT license
- Symfony Update 2.3 LTS
- OpenLayers 2.13 with additional patches
- Switch Services (BaseSourceSwitcher) with menu
- added generic HTML element
- added custom CSS editor for applications
- added accordion container for SidePane
- added screenshot management to application editing
- import/export of applications/sources
- spanish translation

9.35 Version 3.0.3

release date: 17-03-2014

For details have a look at: https://github.com/mapbender/mapbender/issues?milestone=8

- Enhancements for Search-Router für SQL-Suchen (Selectboxes, Distinct)
- WMC Editor and Loader
- WMSLoader Enhancement add WMS via link
- i18n Internationalisation (english / german)
- Sketch to draw temporary objects
- POI Meetingpoint
- Imageexport to generate png or jpg
- Change WMS Collection via button (BaselayerSwitcher)
- Print with overview
- Sidepane with different elements (chnage via button)
- Layertree context menue to change opacity and to zoom to layer
- Open application with parameters (e.g. position)
- ACL for elements
- Added function for validate WMS GetCapabilities documents

9.36 Version 3.0.2

release date: 27-11-2013

For details have a look at https://github.com/mapbender/mapbender/issues?milestone=6

- SearchRouter
- WMC Editor and Loader
- WMSLoader enhancement to load a WMS from a link

9.37 Version 3.0.1

release date: 06-09-2013

For details have a look at https://github.com/mapbender/mapbender/issues?milestone=5

- Kopieren einer Anwendung mit Diensten
- Popup draggable
- PrintClient Erweiterung Druck EPSG 4326, neue Drucklayouts, Druck A4-A0
- Catch login failures to avoid brute force login attempts
- Bug fixes

9.38 Version 3.0.0.2

Bugfix-Release Date: 19-07-2013 For details have a look at: https://github.com/mapbender/mapbender/issues?milestone=4

9.39 Version 3.0.0.1

Bugfix-Release Date: 07-06-2013 For details have a look at: https://github.com/mapbender/mapbender/issues?milestone=3

9.40 Version 3.0.0.0

release date: 29-05-2013

For details have a look at https://github.com/mapbender/mapbender/issues?milestone=1

- Administration Backend for Service, Application, User/Group and security administration
- Backend-/Frontend Design
- Security
- User/Group Administration
- WMS Administration

- Map
- Layertree
- Legend
- Overview Map
- Navigation Toolbar (Zoombar)
- Feature Info
- Coordinates Display
- Copyright
- Line/Area Ruler
- Scale Selector
- ScaleBar
- Spatial Reference System Selector
- GPS-Position
- Print
- Add WMS to application
- Documentation at http://doc.mapbender.org

CHAPTER

TEN

QGIS2MAPBENDER PLUGIN

QGIS2Mapbender is a QGIS plugin to transfer your QGIS Server project on your server and publish the QGIS Server WMS in Mapbender.

For more information visit QGIS2Mapbender on GitHub